



# **Aspera Desktop Client Admin Guide 3.8.0**

Mac OS X

Revision: 1610 Generated: 06/27/2018 14:04

# Contents

<b>Introduction.....</b>	<b>4</b>
<b>What's New?.....</b>	<b>6</b>
<b>Get Started as a Transfer Client.....</b>	<b>7</b>
<b>Comparison of Aspera File Delivery and Synchronization Tools.....</b>	<b>8</b>
<b>Installation and Upgrades.....</b>	<b>10</b>
Requirements.....	10
Before Upgrading or Downgrading.....	10
Product Setup.....	11
Configuring the Firewall.....	12
Testing a Transfer.....	12
Uninstalling.....	15
<b>Transfer Files in the GUI.....</b>	<b>15</b>
Application Overview.....	15
Global Bandwidth Settings.....	17
Enabling a Transfer Proxy or HTTP Proxy.....	19
Adding and Editing Connections.....	23
Exporting and Importing Connections.....	30
Creating SSH Keys in the GUI.....	31
Transferring Content.....	35
Managing Transfers.....	37
Scheduling and Customizing Transfers in Advanced Mode.....	40
Configuring Transfer Notifications.....	42
Using Transfer Notifications.....	48
<b>ascp: Transferring from the Command Line.....</b>	<b>50</b>
Ascp Command Reference.....	50
Ascp General Examples.....	64
Ascp File Manipulation Examples.....	66
Ascp Transfers with Object Storage and HDFS.....	67
Ascp Transfers with ATS and ATCM.....	67
Transfers with Aspera On Demand and Object-Storage-Based Aspera Servers.....	69
Writing Custom Metadata for Objects in Object Storage.....	72
Using Standard I/O as the Source or Destination.....	72
Applying Filters to Include and Exclude Files.....	76
Symbolic Link Handling.....	81
Creating SSH Keys (Command Line).....	83
Client-Side Encryption at Rest (EAR).....	84
Comparison of Ascp and Ascp4 Options.....	85

Ascp FAQs.....	88
<b>ascp4: Transferring from the Command Line with Ascp4.....</b>	<b>91</b>
Introduction to Ascp4.....	91
Ascp4 Command Reference.....	91
Ascp4 Transfers with Object Storage.....	98
Ascp4 Examples.....	99
Using Ascp4 from the GUI.....	99
<b>Appendix.....</b>	<b>99</b>
Restarting Aspera Services.....	99
Testing and Optimizing Transfer Performance.....	100
aclean Reference.....	101
Log Files.....	102
Accessing Shares from the GUI.....	104
Product Limitations.....	104
<b>Technical Support.....</b>	<b>105</b>
<b>Legal Notice.....</b>	<b>105</b>

# Introduction


---

Thanks for choosing Aspera and welcome to the world of unbelievably fast and secure data transfer.

## The Basics

Aspera high-speed transfers begin when an Aspera client authenticates to an Aspera server and requests a transfer. If the client user has authorization, then transfer tools are launched on the client and server and the transfer proceeds.

For example, an IBM Aspera Desktop Client user connects to an IBM Aspera Enterprise Server and initiates a transfer:



Depending on the user's transfer request, files and folders can be transferred to the server from the client (uploaded) or transferred to the client from the server (downloaded). The source and destination can be cloud storage, an NFS or CIFS mount, and IBM Spectrum Scale storage, to name a few.

## What is the Server?

The Aspera server receives transfer requests from Aspera clients, determines if the user has permission to access the server and authorization to the target area of the file system (source or destination with read or write access), and participates in transfers. The server can be:

- an on-premises installation of Enterprise Server, IBM Aspera Connect Server, or IBM Aspera Point-to-Point Client (which permits one client connection),
- an Enterprise Server installed as part of IBM Aspera Faspex, or
- an Enterprise Server deployed in object storage as an IBM Aspera On Demand instance, an IBM Aspera Transfer Service, or an IBM Aspera Transfer Cluster Manager node.

## What is the Client?

The Aspera client is the program that requests a transfer with the Aspera server. Aspera applications that can act as clients include:

- Desktop Client,
- IBM Aspera Drive,
- IBM Aspera Connect web browser plugin,
- IBM Aspera CLI,
- Enterprise Server, Connect Server, and Point-to-Point Client.

## What is FASP?

At the heart of your Aspera ecosystem are the FASP transfer engines `ascp` and IBM Aspera A4. `ascp` maximizes data transport over any network and is particularly suited to large files. It is a powerful command-line tool and also drives transfers started in the GUI.

A4 (`ascp4`) is another command-line transfer tool that is optimized for both large files and transfers of thousands to millions of small files, handling large amounts of file metadata as part of the high-speed transfer.

Both `ascp` and `ascp4` are installed and enabled with your installation of Enterprise Server, Connect Server, Point-to-Point, and Desktop Client applications.

## The Aspera Transfer Server

Your Aspera transfer server is a powerful, customizable hub for your high speed transfer activity. Configuration settings allow you to control which clients have access for uploading or downloading data, how much bandwidth their transfers can use, the priority of those transfers, and how data is secured during and after transfer. The transfer queue can be managed on the fly, enabling you to adjust as priorities change. You can also monitor transfers and receive email notifications when transfer sessions or individual file transfers start and stop.

## The Aspera Server GUI

The Aspera desktop GUI is primarily a client transfer tool, but it also offers a user-friendly interface for managing users and configuring your server. Security settings, bandwidth use policies, and file handling rules can all be set in the GUI. Configurations can be applied to all users (globally), or to individual users.

## Connect Server Web Portal

Connect Server takes an Enterprise Server and makes it even more accessible to clients by hosting a web-based storage directory. Authorized clients can browse files by using any modern web browser, and transfer using the free, automatically-installed IBM Aspera Connect.

## Asconfigurator: The Aspera Configuration Tool

If you are unfamiliar with the XML formatting required for your Aspera server's configuration file, or need to configure settings that are not available in the GUI, you can edit your configuration with confidence by using `asconfigurator`. These commands ensure that the XML structure is correctly maintained when you add or change settings.

## Tap into the Aspera Ecosystem

If you have a variety of data storage systems and internal and external customers who need access to the content in that storage, Enterprise Server with a Connect-enabled license can be incorporated into a scalable Aspera data transfer ecosystem that meets your needs. Your Aspera server can be monitored and managed by IBM Aspera Console, and added as a node to IBM Aspera Faspex, IBM Aspera Shares, IBM Aspera Files, and IBM Aspera for Microsoft SharePoint.

## The Aspera Client Transfer Tools

Your installation includes the following transfer tools, some of which require an additional license for activation.

### The Aspera Client GUI

The Aspera desktop GUI offers a simple, intuitive way to create connections with Aspera servers, and to start and manage your high-speed transfers. The transfer job queue shows real-time progress and allows on-the-fly reordering and bandwidth control.

### The FASP Transfer Engines: `ascp` and `ascp4`

These command line tools enable you to run transfers to any server to which you have access, and to customize the transfers (within the parameters set by the server). They are scriptable, supporting unattended data transfer and custom pre- and post-transfer file processing.

### Hot Folders: Automatic Data Transfer in the GUI

Sending or receiving files can be even easier and faster by using Hot Folders. Available only on Windows, you can set up a Hot Folder to watch for and automatically transfer any new files that are added to that folder. Automatically send files to a server as they are added to a folder on your own desktop, or receive files as they are added to a folder on the server. Transfers use `ascp` and are easily managed from the GUI.

### Watchfolders: Automatic Content Delivery at Any Scale

The Aspera Watch Service and Watchfolders combined create a powerful, efficient system monitoring and automatic transfer tool that can comfortably handle millions of files and "growing" sources. Automatically transfer files as they

are added to a source folder. With a RESTful API interface, you have full programmatic control for custom, automatic transfer processing.

Watchfolders offer the same transfer and bandwidth management options as `ascp`, and can be monitored and managed through Aspera Console. Watchfolders are enabled in your Enterprise Server, Connect Server, or Point-to-Point Client.

### **IBM Aspera Sync: Directory Synchronization at the Speed of FASP**

When everyone needs to see the same files or you need to be sure that every file is replicated, Sync provides a high-speed tool to do it. Unique among Aspera's transfer tools, Sync supports bidirectional synchronization for optimum collaboration and consistency between computers.

Sync uses efficient file system monitoring and change detection to minimize redundant data transfer and to reduce database storage requirements. Sync offers the same transfer and bandwidth management options as `ascp`, and can be monitored and managed through IBM Aspera Console.

Sync is installed with your Enterprise Server, Connect Server, and Point-to-Point Client, but both the client and server require a Sync-enabled license.

## **What's New?**

---

**Note:** Some Aspera product names are in a transition phase. During the transition, Enterprise Server and Connect Server might also be referred to as "IBM Aspera High-Speed Transfer Server", Point-to-Point Client might also be referred to as "IBM Aspera High-Speed Transfer Endpoint", and IBM Aspera Shares and IBM Aspera Faspex might also be referred to as the bundled product "IBM Aspera High-Speed Sharing Server."

### **General**

- Desktop Client no longer requires a license. For upgrades to 3.8.0, existing licenses are overwritten with the unlimited license after a successful upgrade.
- Updated Java for improved GUI performance and security.
- The ALEE service is now available for macOS, enabling entitlement licensing for Aspera servers.
- Connections that are configured in the GUI and Hotfolders can now be set to encrypt data in transit with a specific encryption cipher: AES-128, AES-192, AES-256, or none. The default is AES-128.
- `ascp` and `ascp4` transfers to object storage can now include custom metadata if the object storage supports it (currently S3, Google, Azure, and Swift). Metadata is set using the `--tags` or `--tags64` option with a JSON payload argument. For instructions, see [Writing Custom Metadata for Objects in Object Storage](#) on page 72. (CIM-723)
- A new command-line tool, `aclean`, is a fast method of deleting directories and files from local and object storage. Directories and files can be filtered based on their last modified times, and the tool supports doing a dry run to determine what content will be deleted. For instructions, see [aclean Reference](#) on page 101.
- Connection passwords can now be saved and restored when exporting and importing connections in the GUI.

### **Ascp**

- Transfer sessions that fallback to HTTP now report file IDs in the management stream (as `FaspFileID`).
- When using `stdio-tar://` as the source for an `ascp` transfer, the value for "File:" can be a directory and the directory structure is preserved at the destination. Additionally, `stdio-tar://` can now be used as the destination. For information, see [Using Standard I/O as the Source or Destination](#) on page 72.
- Uploads with a `stdio-tar://` destination can now use transfer tokens for authorization.
- The `stdio-tar://` source file can now specify an offset parameter that indicates where in the destination file the inline raw data should be inserted to overwrite the existing data.

### **Ascp 4**

- The data-streaming capabilities of `ascp4` (powered by FASPStream technology) are now available for High-Speed Transfer Server and High-Speed Transfer Endpoint users. Features include:

- Multiple multicast streams can now concurrently transfer to the same multicast IP address (as long as the multicast port varies) or concurrently transfer to the same multicast port (as long as the multicast IP address varies). (CIM-770)
- TCP providers can be used as a source or destination I/O in command line.
- UDP providers can be used as a source or destination I/O in command line.
- A new parameter, `pktbatch`, can be used to control how UDP datagrams are read and written. By default, `FASPStream` now does a batch read and write of UDP datagrams. Disable the option to read and write one packet at a time.
- The encryption cipher can now be specified on the client command line using `-c cipher`. The server setting overrides the client if the server setting is stronger.
- A4 transfers can now use transfer token authorization. The transfer token must be created by using `astokenngen` with the `--full-paths` option and passed to A4 with the `ASPERA_SCP_TOKEN` environment variable.
- Faster directory scanning on object storage.
- A4 now supports persistent sessions, using the new option `--keepalive`.
- Faster transfers to object storage, particularly for transfers that skip existing files (`-k 1`) or that use file lists.

#### Other Changes

- Mac OS X 10.8, 10.9, and 10.10 are no longer supported.

## Get Started as a Transfer Client

---

Aspera transfer clients connect to a remote Aspera transfer server and request a transfer with that server. Your Aspera application can be used as a client to initiate transfers with Aspera servers, as described in the following steps.

1. Review the system requirements and install Desktop Client.  
See [Requirements](#) on page 10 and [Product Setup](#) on page 11.
  2. Configure the firewall.  
See [Configuring the Firewall](#) on page 12.
  3. Configure transfer preferences.  
You can configure your bandwidth usage, email notification, and proxy settings to apply to all transfers. For more information, see [Global Bandwidth Settings](#) on page 17 and [Enabling a Transfer Proxy or HTTP Proxy](#) on page 19.
  4. Test a locally-initiated transfer to the Aspera demonstration server to confirm your installation and firewall configuration are operational.  
For instructions, see [Testing a Transfer](#) on page 12. This provides a simple walk through of how to set up a connection with a server and transfer.
  5. Configure your email notification preferences.  
You can receive emails when transfer sessions start and finish to keep up-to-date on your transfer progress. For more information, see [Configuring Transfer Notifications](#) on page 42.
  6. If you need to authenticate to the remote server with an SSH key, create an SSH key and send the public key to the server admin.  
For instructions on creating an SSH key, see [Creating SSH Keys in the GUI](#) on page 31 or [Creating SSH Keys \(Command Line\)](#) on page 83.
  7. To run transfers in the GUI, create and configure a connection to the server.  
For instructions, see [Adding and Editing Connections](#) on page 23. If required, configure a proxy ([Enabling a Transfer Proxy or HTTP Proxy](#) on page 19). You can also configure transfer notifications ([Scheduling and Customizing Transfers in Advanced Mode](#) on page 40).
- Once your connection is configured, you can initiate transfers with the server. For instructions, see [Transferring Content](#) on page 35.

8. To run transfers from the command line, review the instructions for the Aspera command line clients.

Your Aspera product comes with two command line clients: `ascp` and A4. They are similar but have different capabilities. For a comparison, see [Comparison of Ascp and Ascp4 Options](#) on page 85.

- For more information about `ascp`, see [Ascp Command Reference](#) on page 50 and [Ascp General Examples](#) on page 64.
- For more information about A4, see [Ascp4 Command Reference](#) on page 91 and [Ascp4 Examples](#) on page 99.

Once you confirm that you can transfer with your server, your basic set up is complete.

For a comparison of automatic transfer tools, see [Comparison of Aspera File Delivery and Synchronization Tools](#) on page 8.

## Comparison of Aspera File Delivery and Synchronization Tools

Your Aspera product includes several transfer tools, besides `ascp` and A4, that can be used for automatic file delivery and synchronization:

- **Hot folders:** a Windows-only, GUI-managed automatic file delivery tool.
- **Watchfolders:** an automatic file delivery tool that is easily managed by using the GUI, IBM Aspera Console, or the Node API.
- **Sync:** a multi-directional synchronization tool for when complete file system synchronization is required.

	Hot Folders	Watchfolders	Sync
Supported platforms	Windows only	Windows macOS Linux AIX Solaris Linux on z Systems BSD Isilon	Windows macOS Linux AIX Solaris Linux on z Systems BSD
Additional license required	No	No	Yes, a Sync-enabled license is required on both endpoints
Interface	Aspera desktop GUI	Aspera desktop GUI, Node API in any command line, command line on the Aspera client, or Console web UI.	Aspera client command line, Console web UI for management only (no creation)
Client applications	Desktop Client Point-to-Point Client Enterprise Server Connect Server	Point-to-Point Client Enterprise Server Connect Server	Point-to-Point Client Enterprise Server Connect Server IBM Aspera Drive
Server configuration required	No	No (only need a Watch Service on server for pull Watch Folders)	Recommended



	<b>Hot Folders</b>	<b>Watchfolders</b>	<b>Sync</b>
Create in Console	No, but you can monitor transfers	Yes, you can create, monitor, and manage	No, but you can monitor Sync jobs and their associated transfer sessions
Transfer modes	<ul style="list-style-type: none"> <li>• Client to server (push)</li> <li>• Server to client (pull)</li> </ul>	<ul style="list-style-type: none"> <li>• Client to server (push)</li> <li>• Server to client (pull)</li> </ul>	<ul style="list-style-type: none"> <li>• Client to server (push)</li> <li>• Server to client (pull)</li> <li>• Client and server (bidirectional)</li> </ul>
File delivery or synchronization	<p>File delivery:</p> <p>Files and folders added to or modified within a Hot folder on the source are automatically sent to the destination folder. Files deleted from the source are not deleted on the destination.</p>	<p>File delivery:</p> <p>Files and folders added to or modified within a Watchfolder on the source are automatically sent to the destination folder. Files deleted from the source are not deleted on the destination.</p>	<p>Synchronization:</p> <p>All file system changes (additions, deletions, and modifications) are synchronized from source to destination (push or pull) or synchronized between source and destination (bidirectional).</p>
File system monitoring	Windows operating system notifications.	File system snapshots collected by the Aspera Watch Service (asperawatchd)	<ul style="list-style-type: none"> <li>• In continuous mode: file system notifications</li> <li>• In scan (on-demand) mode: Sync scans the file system on the source side and compares it to the Sync database</li> <li>• Aspera Watch Service</li> </ul>
Transfer schedules	<ul style="list-style-type: none"> <li>• Immediate (as soon as a file system change in the Hot folder is detected)</li> <li>• On a user-specified schedule</li> </ul>	<ul style="list-style-type: none"> <li>• Immediate (as soon as a difference between snapshots is detected)</li> </ul>	<ul style="list-style-type: none"> <li>• Immediate (in continuous mode or when using Sync with the Aspera Watch Service)</li> <li>• On a user-specified schedule (Sync run as a cron job)</li> </ul>
Growing file support	No	Yes (on Enterprise Server and Connect Server)	No
Database space requirements	None	At least 2 GB free per 1 million files, 3 GB free per 1 million files on Windows	At least 2 GB free per 1 million files, 3 GB free per 1 million files on Windows
Best for	<ul style="list-style-type: none"> <li>• Automatic push and pull delivery with a simple GUI interface that does not require Console</li> </ul>	<ul style="list-style-type: none"> <li>• Automatic push and pull delivery with a simple GUI interface that does not require Console</li> <li>• Managing and monitoring push</li> </ul>	<ul style="list-style-type: none"> <li>• Precise synchronization between two endpoints of all file system changes (including deletions)</li> <li>• Bidirectional synchronization</li> <li>• Very large file sets - up to 100 million items</li> </ul>

	Hot Folders	Watchfolders	Sync
		delivery through Console	across thousands of directories
Limitations	<ul style="list-style-type: none"> <li>Windows only</li> <li>GUI must remain open</li> <li>In pull mode, Hot folders pull files even if they are in use</li> </ul>	<ul style="list-style-type: none"> <li>Transfer rate of millions of small files can become limited by the speed at which database metadata can be written</li> </ul>	<ul style="list-style-type: none"> <li>Continuous mode available only for Windows and Linux sources</li> <li>Transfer rate of millions of small files can become limited by the speed at which database metadata can be written</li> </ul>
More information	<a href="#">Aspera Enterprise Server Admin Guide for Windows</a>	<a href="#">Aspera Enterprise Server Admin Guide</a>	<a href="#">Aspera Enterprise Server Admin Guide</a> or <a href="#">Aspera Sync Admin Guide</a>

## Installation and Upgrades

---

### Requirements

---

System requirements for IBM Aspera Desktop Client:

- Product-specific Aspera license file.
- Mac OS X 10.11, macOS 10.12 (Sierra), 10.13 (High Sierra)
- Screen resolution 1024 x 768 or higher.

### Before Upgrading or Downgrading

---

#### Upgrading

- The Aspera Client installer automatically checks for an older version of the product on your system. If an older version is found, the installer automatically removes it before installing the new version.
- Although the installer performs your upgrade automatically, Aspera highly recommends completing the tasks below before upgrading. If you do not follow these steps, you risk installation errors or losing your former configuration settings.
- You cannot upgrade directly between different Aspera transfer products (such as from Point-to-Point to Desktop Client, or from Point-to-Point to Enterprise Server). To upgrade, you need to back up the configuration, uninstall the product, and perform a fresh install of the new version of the product.

#### Downgrading

Older installers do not check for newer versions of the application. You must prepare your machine as described below then uninstall the newer version before continuing with your downgrade.

#### Preparing for an Upgrade or Downgrade

1. Verify the version of your existing product.

The steps required to prepare for an upgrade may differ depending on your current product version. To view the current product and version, run the following command:

```
$ ascp -A
```

2. Review product release notes.

Review the release notes for the versions that were released since your current version. In particular, the **Breaking Changes** section highlights changes that may require you to adjust your workflow, configuration, or usage.

3. Stop or allow to complete any FASP transfers that were initiated by the computer that you are upgrading.

FASP transfers cannot proceed during your Aspera product upgrade.

- Close the application GUI.
- Stop (and resume after upgrade) or allow to complete any `ascp`, `A4`, or `Sync` transfers in the command line.

4. Back up configuration and settings files.

These files are found in the `etc` and `var` folders. Their location depends on the version of your previous installation.

**Aspera 2.5+**

- `/Library/Aspera/etc/` (contains Configuration files and license info)
- `<home directory>/Library/Application Support/Aspera/Client` (contains Remote Hosts settings)

## Product Setup

---

To install Desktop Client, log into your computer with root permissions.

**Important:** If this is a product upgrade, review all prerequisites described in [Before Upgrading or Downgrading](#) on page 10.

1. Download the IBM Aspera product installer.

Use the credentials provided to your organization by Aspera (not your personal Aspera ID) to access:

<http://downloads.asperasoft.com/en/downloads/2>

If you need help determining your firm's access credentials, contact your Aspera account manager.

2. For product upgrades, ensure you have prepared your machine to upgrade to a newer version.

Although the installer performs your upgrade automatically, Aspera *highly recommends* completing the tasks described in [Before Upgrading or Downgrading](#) on page 10. If you do not follow these steps, you risk installation errors or losing your configuration settings.

3. Run the installer

To start the installation, double-click the installer package. Follow the onscreen instructions to go through the installation process.

4. Installation troubleshooting.

If the installer freezes during installation, another Aspera product might be running on your computer. To stop all FASP transfer-related applications and connections, see [Before Upgrading or Downgrading](#) on page 10.

5. Install Java.

When you run Desktop Client for the first time, you are prompted to install Java because OS X 10.8+ does not come with it pre-installed.

6. For Mac OS X 10.11 and later, set the SSH path for transfer users.

a) Create a file named `environment` for every transfer user in the following location:

```
/Users/username/.ssh/
```

b) Paste the following content into the file:

```
PATH=/bin:/usr/bin:/usr/sbin:/sbin:/usr/local/sbin:/usr/local/bin:/opt/pkgconfig/bin:/Library/Aspera/bin:/Library/Aspera/sbin
```

This sets the PATH variable for remote connections.

c) To allow local transfer users to run ascp commands, paste the same content, prefaced with `export`, into the following file, which you may need to create:

```
/Users/username/.bash_profile
```

For more information, see the Aspera knowledge base article [Workaround to use Aspera transfer servers on Mac OS X 10.11 El Capitan](#).

## Configuring the Firewall

Your Aspera transfer product requires access through specific ports. If you cannot establish the connection, review your local corporate firewall settings and remove the port restrictions accordingly.

### Desktop Client

The following is basic information for configuring your firewall to allow Aspera file transfers. The outbound TCP port for SSH may differ depending on your organization's unique network settings. Although TCP/33001 is the default setting, refer to your IT Department for questions related to which SSH port(s) are open for file transfer. Consult your operating system's documentation for instructions on configuring your firewall. If your client host is behind a firewall that does not allow outbound connections, you will need to allow the following ports:

- **Outbound TCP/33001:** Allow outbound connections from the Aspera client on the TCP port (TCP/33001 by default, when connecting to a Windows server, or on another non-default port for other server operating systems).
- **Outbound UDP/33001:** Allow outbound connections from the Aspera client on the FASP UDP port (33001, by default).
- **Local firewall:** If you have a local firewall on the client (such as `ipfw`), verify that it is not blocking your SSH and FASP transfer ports (such as TCP/UDP 33001).

## Testing a Transfer


To make sure the software is working properly, follow these steps to set up a simple connection with the Aspera Demo Server and test download and upload transfers.

1. Launch the application.  
Click **Macintosh HD > Applications > Aspera Client**.
2. Add the Aspera Demo Server in the Connection Manager.  
Click **Connections**:



In the **Connection Manager**, click **+** to add a new connection, click **OK** to create a standard connection, and enter the following information, leaving the other options with their default values or blank:

Field	Value
Host	demo.asperasoft.com
User	aspera
Authentication (Password)	demoaspera





3. Test your connection to the remote server.


Click **Test Connection** to determine whether you can reach the remote server with the settings you configured. An alert box opens and reports whether the connection is successful.

4. Connect to the Demo Server and download test files.

From the main window, select the demo server entry and click the **Connect** button.




On the server file browser (right panel), browse to the folder /aspera-test-dir-large, select the file 100MB, and click  to download it to your local machine.



You should see the session appear in the **Transfer** pane.

##### 5. Upload to the Demo Server

Select the same file (100MB) on the local file browser (left panel), go to the folder /Upload on the Demo Server, and click  to upload it.

## Uninstalling

To remove all binaries for Desktop Client installed on the computer, enter the following command in a Terminal:

```
$ sudo /Library/Application\ Support/Aspera/uninstall
```


## Transfer Files in the GUI

### Application Overview

#### Launching the Application

To launch the application, go to **Macintosh HD > Applications > Aspera Client**.


#### The Application GUI



Item	Description
A	Click <b>Transfer</b> to enter the transfer viewing mode. This is the default view when you launch the application, which shows the local and remote file browsers. For more information, see <a href="#">Transferring Content</a> on page 35.
B	Select a transfer from the bottom pane and click <b>Details</b> to enter the transfer details viewing mode. This view shows the details of the selected transfer session, as well as the transfer control options. For more information, see <a href="#">Managing Transfers</a> on page 37.
C	Click <b>Connections</b> to open the <b>Connection Manager</b> window in which you can manage the remote endpoints. For more informations, see <a href="#">Adding and Editing Connections</a> on page 23.
D	Click <b>Preferences</b> to set the local computer's default transfer settings, such as the FASP global bandwidth and the number of simultaneous transfers in the queue, and the SMTP server's information for transfer notifications.
E	Browse the local file system to view files to transfer.
F	When not connected, a list of the saved connections is displayed. When connected (by clicking on a Connection Name and clicking <b>Connect</b> ), browse the remote file system.
G	Display previous, ongoing, and queued transfers. Manage the priority.

### The File Browser

All options in the File Browser, including the file browser's contextual menu (Mouse right-click):



Item	Description
A	Path indicator/selector.
B	Go to the parent directory.
C	Create a new folder.




Item	Description
D	Choose between the list views and the detail view.
E	Create a new folder.
F	View the advanced upload or download window.
G	Decrypt the selected file if it is encrypted with the content protection.
H	Choose between the detail or the list views. Refresh the folder.
I	Options to manipulation the selected files.
J	Show the selected files' properties.

## Global Bandwidth Settings


Aspera FASP transport has no theoretical throughput limit. Other than the network capacity, the transfer speed can be limited by user-configured rate settings and the resources of the local and remote machines.

To set limits on transfer bandwidth and the number of concurrent FASP transfers:

1. Launch the application with administrator privileges and click **Tools > Global Preferences**.



2. Click **Transfers**.



3. To limit total bandwidth usage by FASP uploads and downloads, edit **System-Wide Settings**.

System-wide settings set the aggregated bandwidth cap for all FASP transfers on this computer.

To override the default bandwidth limits, under **System-Wide Settings** select the boxes next to **Limit Download Bandwidth** and **Limit Upload Bandwidth** and enter new values in the fields. The global settings for download and upload bandwidth limits cannot be reset by non-admin users. However, users can view the global limit from the **Preferences > Transfers** dialog.

The maximum number of concurrent upload transfers and download transfers. The initial download and upload rates for all transfers. Item The initial download and upload rates for all transfers. Item

4. To set default target rates for all users, edit **Default Target Rate**.  
Non-admin users can adjust their personal default target rates above or below the global default value.
5. To limit the number of active transfers, edit **Maximum Active Transfers**.  
Non-admin users can adjust their personal maximum active transfers above or below the global default value.
6. Click **OK** to activate your changes.


## Enabling a Transfer Proxy or HTTP Proxy

---

If, for network security reasons, you are behind a transfer proxy server, you can enable the proxy for file transfer by configuring settings in the **Preferences** dialog. If you have admin privileges, you can enable transfer proxies for all users by setting global preferences. If you are a non-admin user, you can override global transfer-proxy settings for your own account, including enabling or disabling the feature.

By default, proxy is disabled.

Open the proxy configuration dialog by clicking **Tools** then **Global Preferences > Proxy** or **Preferences > Proxy**, or by clicking **Preferences > Proxy**. Clicking **Preferences** opens the user-account proxy settings, but, if you have permission, you can click **Global Preferences** to access those settings.




### Configuring Global Transfer and HTTP Proxy Settings

You must have admin privileges to set global preferences.

To enable a transfer proxy:

1. Go to **Global Preferences > Proxy**.
2. Select **Enable transfer proxy**.
3. Enter the proxy server's hostname or IP address and port number.
4. Select **Secure** if your proxy server allows secure connections.
5. Enter your username and password to authenticate with your proxy server.



To enable HTTP proxy:

1. Go to **Global Preferences > Proxy**.
2. Select **Enable HTTP proxy**.
3. Enter the HTTP proxy's hostname or IP address and port number.
4. If your HTTP proxy requires authentication, select **Authenticated** and enter the username and password for your HTTP proxy.




To clear all settings, click **Restore System Defaults**.

### User Proxy Settings

To override the global settings, edit the proxy settings for your account. Click **Preferences > Proxy**. The values are those that you inherited from the global proxy settings.


To configure user transfer proxy settings:

1. Select or clear **Enable transfer proxy** to enable or disable transfer proxy.
2. Enter the proxy server's hostname or IP address and port number.
3. Select **Secure** if your proxy server allows secure connections.
4. Enter your username and password to authenticate with your proxy server.



To configure user HTTP proxy settings:

1. Select or unselect **Enable HTTP proxy**.
2. Enter the HTTP proxy's hostname or IP address and port number.
3. If your HTTP proxy requires authentication, select **Authenticated** and enter the username and password for your HTTP proxy.



To revert all user settings to the global values, click **Restore Defaults**.

## Adding and Editing Connections

To transfer with an on-premises Aspera Enterprise Server, Connect Server, or Point-to-Point Client, or with a cloud-based Aspera server through the Aspera Transfer Service or an Aspera Transfer Cluster node, add it as a connection in the **Connection Manager**. The following instructions describe how to create and configure a connection and edit or delete connections.


To connect with cloud storage, you must meet the following prerequisites:


- You have permissions to access the cloud storage and the necessary authentication information.
- To transfer files with an S3 storage device using an S3 direct connection, the user must have a restriction rather than a docroot set on the server.


Once you create connections, you can export and import connection lists. For instructions, see [Exporting and Importing Connections](#) on page 30.



To create a new connection:

1. Start the application.  
Click **Macintosh HD > Applications > Aspera Client**.
2. To open the **Connection Manager**, click **Connections**.



3. Click  to create a new connection.



Click  to duplicate a selected connection (to copy all information into a new profile) and  to delete a connection profile.


4. In the **Create Connection** popup, select the type of connection.
- **Create a standard connection:** Create a connection that does not use the Aspera Transfer Service (ATS) to connect to cloud storage.
  - **Create a connection with a new Aspera Transfer Service (ATS) Access Key:** Create a connection to cloud storage and generate a new ATS access key to authenticate the connection. Select the storage type from the drop-down menu, and enter the required authentication information (depending on storage type). Entering a name is optional; it can be edited in the **Connection Manager**.



- **Create a connection with an existing ATS Access Key:** Create a connection to cloud storage with an existing Aspera access key. Enter the Aspera access key ID and secret. Entering a name is optional; it can be edited in the **Connection Manager**.
5. Configure the connection name, if desired.

By default, local connections are named **username@host** and ATS connections are named the host address.

To name or rename a connection, click the connection name and enter the new name in the popup. Click **OK** to save your changes.



6. Configure the required settings for the connection.

To activate a local or ATS connection, only **Host**, **User**, and **Authentication** are required.

To activate a connection to object storage, you must also select the type of storage for **Storage Type** and enter your credentials.

On the **Connection** tab, enter the following information:

Connection Option	Description
Host	The server's address, such as 192.168.1.10 or companyname.com. For ATS connections, enter the URL for the ATS service and the port for the Node service, such as <code>https://ats-aws-us-west-2.aspera.io:443</code> .
User	The transfer user's username or, for ATS connections, the Aspera Access Key ID.
Authentication	For standard connections, choose password or public key authentication. To use public key-based authentication, see <a href="#">Creating SSH Keys in the GUI</a> on page 31. For ATS connections, enter the Aspera Access Key secret in the <b>Password</b> field.

Connection Option	Description
Storage Type	<p>The default option is local storage. Use the drop-down menu to configure object storage. Connecting to object storage requires an ALEE-enabled Aspera server on the remote storage.</p> <p>Supported object storages include the following:</p> <ul style="list-style-type: none"> <li>• <b>Akamai NetStorage</b></li> <li>• <b>Amazon S3:</b> Requires your Access Id, Secret Access Key, and bucket path. The local machine must be reasonably time-synchronized in order to communicate with the Amazon servers. You can also select the <b>Advanced</b> button to modify the following settings: <ul style="list-style-type: none"> <li>• <b>Host:</b> Amazon S3 hostname (default: s3.amazonaws.com).</li> <li>• <b>Port:</b> Default is port 443.</li> <li>• <b>HTTPS connection for file browsing:</b> Enable for secure browsing.</li> <li>• <b>Server-side file encryption:</b> Enable for AES256 encryption.</li> <li>• <b>Reduced redundancy storage class:</b> Assign objects to a to the "reduced redundancy" storage class (durability of 99.99%).</li> </ul> </li> <li>• <b>Google Storage:</b> Requires your Project Number and bucket path.</li> <li>• <b>Limelight:</b> Requires your Account, Username, and Password.</li> <li>• <b>IBM Cloud Object Storage - Swift:</b> Requires your User name, API Key (Password), and Authentication Endpoint.</li> <li>• <b>Rackspace Swift:</b> Requires your Storage Account and Access Key.</li> <li>• <b>Windows Azure:</b> Requires your Storage Account and Access Key.</li> </ul> <p>Azure storage is set to use the Azure block blob REST API by default. To specify the REST API for page blobs, enter your account credentials then click <b>Advanced</b>. Select <b>PAGE</b> from the dropdown menu next to <b>Api</b> and click <b>OK</b>.</p> <ul style="list-style-type: none"> <li>• <b>Windows Azure SAS:</b> Requires your Shared URL.</li> <li>• <b>Azure Files:</b> Requires your File service endpoint and password.</li> </ul>

7. Configure other connection settings, if needed.

On the **Connection** tab, configure non-default connection settings by editing any of the following settings:

Connection Option	Description
Target Directory (or Bucket Path for most object storage)	The default directory when connecting to this computer. When left blank, browsing the remote host brings up either the user's docroot or the last-visited folder. When a path is set, the connection opens to the exact directory.
Advanced Settings > SSH Port (TCP)	The TCP port for SSH connections. Default: 33001. If the application cannot connect on 33001, it automatically attempts a connection on port 22. If the connection on 22 succeeds, the setting is updated to 22.
Advanced Settings > fasp Port (UDP)	The UDP port for FASP transfers. Default: 33001.
Advanced Settings > Connection Timeout	Time out the connection attempt after the specified time.
Test Connection	Click to test the connection to the remote server with the settings you configured.

8. Configure the connection's transfer settings, if needed.

On the **Transfer** tab, configure non-default transfer settings by editing any of the following settings:

Transfer Option	Description
Transfer Name	Select from the following options: <b>Automatically generate</b> allows the user interface to generate the transfer name; <b>Automatically generate and add prefix</b> uses auto-generated name with a customizable prefix; <b>Specify</b> uses the user-specified name.
Policy	<p>Select the FASP transfer policy.</p> <p><b>high</b></p> <p>Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, the transfer rate is twice as fast as a fair-policy transfer. The <i>high</i> policy requires maximum (target) and minimum transfer rates.</p> <p><b>fair</b></p> <p>Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, bandwidth is shared fairly by transferring at an even rate. The <i>fair</i> policy requires maximum (target) and minimum transfer rates.</p> <p><b>low</b></p> <p>Adjust the transfer rate to use the available bandwidth up to the maximum rate. Similar to fair mode, but less aggressive when sharing bandwidth with other network traffic. When congestion occurs, the transfer rate is reduced to the minimum rate until other traffic decreases.</p> <p><b>fixed</b></p> <p>Attempt to transfer at the specified target rate, regardless of network or storage capacity. This can decrease transfer performance and cause problems on the target storage. Aspera discourages using the <i>fixed</i> policy except in specific contexts, such as bandwidth testing. The <i>fixed</i> policy requires a maximum (target) rate.</p>
Speed	Select <b>Override default transfer rate settings</b> to specify the transfer rate. The target rate is constrained by the global bandwidth settings; for more information, see <a href="#">Global Bandwidth Settings</a> on page 17.
Retry	<p>Select to automatically retry the transfer after a recoverable failure for a set amount of time, in seconds, minutes or hours. You may set the initial and maximum retry intervals by clicking the <b>More Options</b> button.</p> <ul style="list-style-type: none"> <li>• <b>Initial interval:</b> The first retry waits for the initial interval. Input in seconds, minutes or hours.</li> <li>• <b>Maximum interval:</b> After the initial interval, the next interval doubles until the maximum interval is met, and then stops retrying after the retry time is reached. Input in seconds, minutes or hours.</li> </ul> <p>For example, if the retry is set for 180 seconds, the initial interval is 10 seconds, and the maximum interval is 60 seconds, then the transfer will retry at 10, 30, 70, 130, and 180 seconds after the first try, such that the interval progression is 10, 20, 40, 60, 60, and 50 seconds. The last interval is not the maximum because the retry period ends with a final retry.</p> <p>As another example, if the retry is set for 600 seconds, the initial interval is 30 seconds, and the maximum interval is 120 seconds, then the transfer will retry at 30, 90, 210, 330, 450, 570, and 600 seconds after the first try, such that the interval progression is 30, 60,</p>

Transfer Option	Description
	120, 120, 120, 120, and 30 seconds. Again, the last interval is not the maximum because the retry period ends with a final retry.
Show Advanced Settings	Click <b>Show Advanced Settings</b> to edit the following options: <ul style="list-style-type: none"> <li>• <b>Specify FASP datagram size (MTU):</b> By default, the detected path MTU is used. Select to specify a value between 296 and 10000 bytes.</li> <li>• <b>Disable calculation of source files size before transferring:</b> Select to turn off job size calculation on the client side, if allowed by the server.</li> </ul>

9. Configure tracking and email notifications, if needed.

On the **Tracking Tab**, configure non-default transfer settings by editing any of the following settings:

Tracking Option	Description
Generate delivery confirmation receipt	Select to create a delivery receipt file in the specified location.
Send email notifications	Send email notifications based on specified events (start, complete, and error). See <a href="#">Using Transfer Notifications</a> on page 48 for more information.

10. Configure filters to automatically exclude certain files from transfers with this connection, if needed.

On the **Filters** tab, click **Add** and enter the pattern to exclude files or directories with the specified pattern in the transfer. The exclude pattern is compared with the whole path, not just the file name or directory name. Two special symbols can be used in the setting of patterns:

Filter Symbol	Name	Description
*	Asterisk	Represents zero to many characters in a string, for example * .tmp matches .tmp and abcde .tmp.
?	Question mark	Represents one character, for example t?p matches tmp but not temp.

For more information on filter rule syntax, see [Applying Filters to Include and Exclude Files](#) on page 76.

11. Configure security settings, if needed.

On the **Security** tab, configure non-default transfer settings by editing any of the following settings:

Security Option	Description
Encryption	Select the encryption cipher ( <b>AES-128</b> , <b>AES-192</b> , or <b>AES-256</b> ) to use for encrypting data in transit, or disable encryption by selecting <b>none</b> .  Aspera strongly recommends using encryption. However, encryption may decrease performance, especially at higher transfer speeds and with slower computers.
Content Protection	Select <b>Encrypt uploaded files with a password</b> to encrypt the uploaded files with the specified password (client-side encryption at rest). The protected file has the extension <code>.aspera-env</code> appended to the file name. Anyone downloading the file must have the password to decrypt it.  Select <b>Decrypt password-protected files downloaded</b> to prompt for the decryption password when downloading encrypted files.  For more information about client-side encryption at rest, see <a href="#">Client-Side Encryption at Rest (EAR)</a> on page 84.

12. Configure file handling, if needed.

On the **File Handling** tab, configure non-default transfer settings by editing any of the following settings:


File Handling Option	Description
Resume	<p>Select <b>Resume incomplete files</b> to enable the resume feature. Select the file comparison method from the <b>When checking files for differences</b> dropdown menu:</p> <ul style="list-style-type: none"> <li>• <b>Compare file attributes</b> - Compares the sizes of the existing and original file. If they are the same, then the transfer resumes, otherwise the original file is transferred again.</li> <li>• <b>Compare sparse file checksums</b> - Performs a sparse checksum on the existing file and resumes the transfer if the file matches the original, otherwise the original file is transferred again. (Default)</li> <li>• <b>Compare full file checksums</b> - Performs a full checksum on the existing file and resumes the transfer if the file matches the original, otherwise the original file is transferred again.</li> </ul> <p>Under <b>When a complete file already exists at the destination</b>, select an overwrite rule when the same file exists at the destination. By default, files on the destination are overwritten if different from the source.</p>
File Attributes	<ul style="list-style-type: none"> <li>• Select <b>Preserve Access Time</b> to set the access time of the destination file to the same value as that of the source file.</li> <li>• Select <b>Preserve Modification Time</b> to set the modification time of the destination file to the same value as that of the source file.</li> <li>• Select <b>Preserve Source Access Time</b> to keep the access time of the source file the same as its value before the transfer.</li> </ul> <p><b>Note:</b> Access, modification, and source access times cannot be preserved for node and Shares connections that are using cloud storage.</p>
Source Handling	<p>Select <b>Automatically delete source files after transfer</b> to delete the files that transferred successfully from the source.</p> <p>Select <b>Automatically move uploaded source files to a directory after transfer</b> and specify the location on the source machine to which they should be moved. Only a path to an existing location on the client can be specified.</p> <p>Select <b>Delete empty source subdirectories</b> to remove empty subdirectories from the source once the files that they contain transfer successfully. This option is usually used to clean up the Hot Folder when source files are moved or deleted after transfer.</p>

13. Click **OK** to save your changes.


Changes are not saved until you click **OK**. Selecting **Cancel** will discard any unsaved changes made in the Connection Manager, including the addition and removal of connections.

14. Connect to the remote host.

Double-click the connection name, or select it and click **Connect**.



### Editing and Deleting Connections

Click **Connections** and select the connection you want to edit or delete. Edit the settings or click  to delete the connection. Deleting connections cannot be undone. When in doubt, export the connections as a backup before deleting a connection.

## Exporting and Importing Connections

Connections, and optionally their passwords, can be exported and imported as a text file, and the text file can be password protected.


### Note:

- If you are exporting a connection that uses keys, back up the keys manually and import separately.
- A shared connection that is exported or imported by a non-administrator is imported as a regular connection (not as a shared connection).
- Email templates are not exported with the connection.

### Export Connections

To export your connection list:

1. Right-click the remote server panel and click **Export**.



2. Enter the following information:

- **Destination:** Enter or browse to the location on your computer where to save the file.
- **Options:** The passwords associated with your connections can be exported. Select if you do not want to export passwords, export passwords without obscuring the passwords (**Export passwords in clear**), or export encrypted passwords (**Encrypt passwords**).
- **Password:** Required if **Encrypt passwords** is selected. When the connections are imported, use the password to decrypt the connection passwords.

3. Click **OK** to export your connection information to the file.

### Import Connections

To import a connection list:

1. Right-click the remote server panel and select **Import**.
2. Enter the following information:
  - **Source file:** The file with the exported connections.
  - **Options:** Select the appropriate option, depending on how the connections were exported.

- **Password:** If you select the **Passwords are encrypted** option, enter the password that was set when the connections were exported.
3. Click **OK** to import the connection information.
  4. Before deleting the source file, confirm that the import process was successful by testing your connections.

## Creating SSH Keys in the GUI


Public key authentication (SSH Key) is a more secure alternative to password authentication that allows users to avoid entering or storing a password, or sending it over the network. Public key authentication uses the client computer to generate the key pair (a public key and a private key). The public key is then provided to the remote computer's administrator to be installed on that machine. To use your Aspera product's transfer-client functionality with public key authentication, follow the steps below.

You can use the application GUI to generate key pairs and to import existing key pairs. You can also generate key pairs using the command line; for instructions, see [Creating SSH Keys \(Command Line\)](#) on page 83.


1. Launch the application.

Start the application by clicking **Macintosh HD > Applications > Aspera Client**.

2. In the menu bar, click **Tools > Manage Keys**.



3. In the SSH Keys dialog, click **+** to create a new key pair.



The SSH Keys dialog is also available from the **Connection** tab in the Connection Manager. When you select **Public Key** for authentication, the **Manage Keys** button appears; clicking it opens the SSH Keys dialog.

4. In the **New SSH Key Pair** window, enter the requested information.

Field	Description
Identity	Name your key pair, such as with your user name.
Passphrase	(Optional) Set a passphrase on your SSH key, which will be prompted for whenever it needs to use the key. If you don't want the user to be prompted for passphrase when logging in, leave this field blank.
Type	Select RSA (default) or DSA key. Aspera strongly recommends using the more secure RSA-type key.
Access	When sharing a connection with public key authentication, or a connection that is has a Hot Folder (on Windows machines), this option must be checked.






Click **OK** when finished. The public key is displayed in the window and you may copy it to a clipboard or export it to a file that is easy to locate. The key is automatically saved as a file named *identity.pub* in the following location (in the example below, the public key filename is *id\_rsa.pub*):

```
/Users/username/.ssh/id_rsa.pub
```

5. Distribute the public key.

Provide the public key file to your server administrator so that it can be set up for your server connection.

To copy or export the public key, select the key in the **SSH Keys** window, click **Copy Public Key to Clipboard**, and paste the string into an email to send to the server administrator, or click **Export to File** and save the public key as a file.




6. Set up connections using public key authentication.


When your public key has been installed on the remote host by its server administrator, click **Connections** to open the Connection Manager.




Select the connection for which you want to set up the key. In its **Connection** tab, select the **Public Key** Authentication option and select the key from the drop-down menu.



### Importing keys:

To import keys created outside the GUI, go to **Tools > Manage Keys** to open the **SSH Keys** dialog. Click the  button in the upper-left corner of the dialog to open a file browser. You can import the key pair by selecting either the private key or the public key; this will copy both keys into the user's `.ssh` directory. You cannot import a key pair if a key pair with the same identity already exists in the `.ssh` directory.

Imported key pairs can be shared with other users. In the SSH Keys dialog, select a key and click the  button to open the **Edit SSH Key Pair** dialog. Select **Access** to allow shared connections to use this key. Shared keys are moved to the Enterprise Server `etc` directory.

## Transferring Content

The GUI provides an easy, intuitive way to transfer content between the local computer and a remote host. In order to transfer with a remote host, first create a connection to it, as described in [Adding and Editing Connections](#) on page 23.

**Note:** Do not use the following characters in file or folder names:


`/ \ " : ' ? > < & * |`

They can produce unpredictable transfer behavior.

Once a transfer is started, you can manage the transfer rate, transfer policy, and priority. For information, see [Managing Transfers](#) on page 37.

### Connect and Transfer


To connect to the remote host, double-click the connection in the Connection panel, or select it and click **Connect**. In the connections panel, the **Target Directory** shows a specific path if the target directory is set, or the last-visited folder if no target directory is set. For instructions on configuring the target directory, see [Adding and Editing Connections](#) on page 23.



To transfer content to or from the remote computer, select the content to transfer and do any of the following:


- click the upload or download arrow
- drag and drop the files between the windows
- copy and paste the files between the windows


You can also initiate an upload using drag-and-drop from the Finder to the right (remote) browser panel.



### Upload Without Browsing the Remote Host

If the connection has a target directory set on the remote host (see [Adding and Editing Connections](#) on page 23), you can upload content without browsing the remote computer. To do so, select content from the left panel (local),


select the connection name from the right panel (remote) and click  to push the content to the remote computer's target directory.





## Managing Transfers

### The Transfers Panel: Start, Stop, and Reorder Transfers

Once the transfer starts, a progress bar will appear in the **Transfers** panel. You can manage transfer behavior with the following actions:

Click  to start the selected transfer.

Click  to stop the selected transfer.

Click  to delete the selected transfer.

If you have multiple ongoing transfers, use the  and  to change the selected transfer's priority. The # field indicates the transfer's order in the queue.

### The Details View: Adjust Transfer Rates and Policies of Active Transfers

The **Details** button provides additional oversight and control (if you have permission) over transfers. Select a transfer session from the **Transfers** panel and click **Details** to view details and adjust settings.



The **Details** display shows the following information:

The screenshot displays the Aspera GUI for a 2GB file transfer. At the top left, the file size '2GB' is shown. Below it are two tabs: 'Details' (labeled A) and 'Files' (labeled B). The 'Details' tab is active, showing the following information:

- Status:** Transferring at 9.7 Mbps, 27m 4s remaining (ETA: 5:19 PM)
- Statistics:**
  - Size: 151 / 2048 MB (resumed from 81.2 MB)
  - Files: 0 / 1
  - Average Speed: 10.5 Mbps
  - Elapsed: 56s (started at 4:51 PM)
  - RTT Delay: 264ms

At the top right, there are transfer controls (labeled C):
 

- Target Rate:** 10.05 Mbps
- Minimum Rate:** 0 Mbps
- Policy:** Fair

 Below these controls is a graph (labeled D) showing the transfer rate over time. The y-axis ranges from 0.0 Kbps to 10.0 Mbps. The graph shows a blue line that starts at 0, rises to approximately 10 Mbps, and then fluctuates slightly around that level.



Item	Name	Description
A	Details (tab)	Transfer details, including status (rate and ETA) and statistics (session size, files transferred vs. total files to be transferred, average speed, time elapsed, RTT delay and average loss in percent).
B	Files (tab)	All files being transferred in this session, along with each files' size and transfer progress.
C	Transfer controls	<p>Set the FASP transfer policy and transfer rate, if allowed.</p> <p><b>high</b></p> <p>Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, the transfer rate is twice as fast as a fair-policy transfer. The <b>high</b> policy requires maximum (target) and minimum transfer rates.</p> <p><b>fair</b></p> <p>Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, bandwidth is shared fairly by transferring at an even rate. The <b>fair</b> policy requires maximum (target) and minimum transfer rates.</p> <p><b>low</b></p> <p>Adjust the transfer rate to use the available bandwidth up to the maximum rate. Similar to fair mode, but less aggressive when sharing bandwidth with other network traffic. When congestion occurs, the transfer rate is reduced to the minimum rate until other traffic decreases.</p> <p><b>fixed</b></p> <p>Attempt to transfer at the specified target rate, regardless of network or storage capacity. This can decrease transfer performance and cause problems on the target storage. Aspera discourages using the <b>fixed</b> policy except in specific contexts, such as bandwidth testing. The <b>fixed</b> policy requires a maximum (target) rate.</p>

Item	Name	Description
		<b>Important:</b> If <code>--policy</code> is not set, <code>ascp</code> uses the server-side policy setting ( <code>fair</code> by default).
D	Transfer Monitor	The transfer graph. Use the sliders on the vertical axis to adjust the transfer rate up or down (if allowed).

## Configuring Transfer Preferences

If you have administrator privileges, you can set the target transfer rate for all users from the **Global Preferences** dialog. As an individual user, you can override the global settings from **My Preferences**.

To update these settings, go to **Tools > Global Preferences** or **Tools > Preferences**. You can also open **My Preferences** from the **Preferences** button in the upper-right corner of the application's main window; from there you can also reach the **Global Preferences** dialog by clicking **Global Preferences**.



The following options are available under the **Transfers** tab:


Item	Description
Global Bandwidth Limits	The aggregated bandwidth cap for all FASP transfers on this computer.
Default Target Rate	The initial download and upload rates for all transfers.
Maximum Active Transfers	The maximum number of concurrent upload transfers and download transfers.

For information about **Email** settings, see [Configuring Transfer Notifications](#) on page 42.

## Scheduling and Customizing Transfers in Advanced Mode

You can start a transfer in advanced mode to set per-session transfer options, such as filters, security, and scheduling, that override the default transfer settings.

To initiate a transfer in advanced mode, right-click a file or folder to open the context menu and select **Upload** (in the client panel) or **Download** (in the server panel).



The advanced transfer dialog includes the following configuration tabs:

Tab	Description
Transfer	The transfer session-related options, such as the transfer speed and retry rules.
Tracking	Options for tracking the transfer session, including the confirmation receipt and the email notifications.
Filters	Create filters to skip files that match certain patterns.
Security	Enable the transfer encryption and the content protection.
File Handling	Set up resume rule, preserve transferred file attributes, and remove or move source files.
Scheduling	Schedule this transfer.

**Note:** All configuration tabs, except **Scheduling**, are identical to those in the **Connection Manager**. For information on these tabs, see [Adding and Editing Connections](#) on page 23. The **Scheduling** tab is described below.

### Scheduling

To enable transfer scheduling, select **Schedule this transfer**. When finished, click **Transfer**. The following scheduling options are available in the **Transfer repeats** dropdown menu:

**Does not repeat**

Set the time and date for a single transfer.



**Daily**

Set the time for a daily transfer. For **End repeat**, select **Never** to continue daily transfers indefinitely, or **On** and set an end date and time.

**Monday-Friday**


Set the time for a daily transfer only on weekdays. For **End repeat**, select **Never** to continue daily transfers indefinitely, or **On** and set an end date and time.

**Weekly**

Select the time and days of the week for a repeating transfer. For **End repeat**, select **Never** to continue weekly transfers indefinitely, or **On** and set an end date and time.


**Periodically**

Set the frequency to repeat the transfer, in minutes.



Click **Transfer** to submit the scheduled transfer. The transfer is then listed under the Transfers tab, along with an icon (📅) under the # column.

To modify the transfer, right-click it and select **Edit** to view the transfer settings.



**Note:** When scheduling transfers, ensure that the application is running. Scheduled transfers do not run when the application is closed.


## Configuring Transfer Notifications

Transfer notification emails are triggered by three transfer session events: start, completion, and error. These emails are generated from default or customized mail templates.

**Note:** The GUI must remain open for transfer notification emails to send. Closing the GUI stops email notifications.

The following instructions describe how to configure the SMTP server and to create or modify your email templates.

1. Run Aspera Client with `root` permissions..  
Go to **Macintosh HD > Applications > Aspera Client**
2. Open **Global Preferences** by clicking **Tools > Global Preferences**.




3. Click **Mail** to configure global email notification settings.

To turn on email notifications for all users, select **Enable email notifications**. When email notifications are enabled you must enter the email address from which the notifications are sent in the **From Address** field and enter the outgoing email server host name in the **Host** field. The other values are optional. To test your settings, click **Send test email**, which sends a test message to the **From Address**.

The screenshot shows the 'Global Preferences' dialog box with the 'Mail' tab selected. The 'Default Settings for All Users' section includes a checked checkbox for 'Enable email notifications'. Under the 'Identity' section, the 'Name' field contains 'Video Team', the 'From Address' field contains 'videoteam@acme.com', and the 'Reply-To Address' field is empty. Under the 'Outgoing Server' section, the 'Host' field contains 'smtp.acme.com', the 'Port' field contains '25', the 'Connection' section has 'Use TLS' checked, and the 'Authentication' section has 'Open' selected. The 'User' and 'Password' fields are empty. There are buttons for 'Send test email', 'Restore System Defaults', 'Cancel', and 'OK'.


4. Set your personal mail preferences.

To override the global mail settings and configure personal mail settings, click **Tools > Preferences** or click **Preferences**:




Click **Mail** and edit the inherited global default values. To restore your settings to global values, click **Restore Defaults**.

- Open the **Mail Templates** window by clicking **Tools > Mail Templates**.



- To create a new template, click **+**, or to edit an existing template, select the template and click **✎**.



- For new templates, name the template and select its base template. Select an existing template from the **Based On** menu. Click **OK**.
- Edit the template text.

The **Edit Template** window has four fields:

Field	Description
Name	The template name.
HTML	The HTML mail body. Click <b>Insert Image</b> to insert an image into the template. The image is copied to the template directory. Preview the template by clicking <b>Preview</b> .

Field	Description
Text	The plain text mail body. Preview the template by clicking <b>Preview</b> .
Access	Select <b>Share this template with all users on this computer</b> to allow other system users to access this template.

**Edit Template**

Name:

HTML:

```
<html lang="en">
<head>
  <meta http-equiv="Content-Type" content="text/html">
  <style type="text/css">
  </style>
</head>
<body>
```

Text:

```
#foreach ($event in $notifications.getEvents())
=====
Aspera Transfer Notification
=====
#if ($event.isFailed())
```

Access:  Share this template with all users on this computer

The mail template supports MIME (Multipurpose Internet Mail Extensions) multipart messages. You can edit both the HTML and plain text versions of the mail body. The templates are rendered by Apache Velocity (for more information, see the Apache Velocity User Guide at <http://velocity.apache.org/>). Templates use two predefined variables:

- `$formatter` - Contains some utility methods
- `$notifications` - Holds the transfer notifications

To iterate over notifications, use a `foreach` loop. A `foreach` loop generates content for each iteration of the loop. In the following example, a local `$event` variable is declared for use within the `foreach` loop:

```
#foreach ($event in $notifications.getEvents())
...

```

```
#end
```

To generate content only under specific conditions, use a conditional statement. To construct a conditional statement, use `#if`, `#else`, and `#end`, with the following syntax:

```
#if
...
#else
...
#end
```

All conditional statements are categorized in four parts: the conditional (what must occur to trigger the action), session information (what action is triggered), time, and statistics.

### Conditional

Use conditional tests in an `if` statement. For example:

```
#if ($event.isFailed())
...
#end
```

Statement	Description
<code>\$event.isStarted()</code>	If the transfer session is started.
<code>\$event.isCompleted()</code>	If the transfer session is completed.
<code>\$event.isEnded()</code>	If the transfer session is ended.
<code>\$event.isFailed()</code>	If the transfer session is failed.

### Session Information

Statement	Description
<code>\$event.getSourceHost()</code>	The source host name (or host address if the host name is not discoverable).
<code>\$event.getSourceHostAddress()</code>	The source host address.
<code>\$event.getSourcePaths()</code>	The source file path.
<code>\$event.getDestinationHost()</code>	The destination host name (or host address if the host name is not discoverable).
<code>\$event.getDestinationHostAddress()</code>	The destination host address.
<code>\$event.getDestinationPath()</code>	The destination file path.
<code>\$event.getInitiatingHost()</code>	The session-initiating host name (or host address if the host name is not discoverable).
<code>\$event.getInitiatingHostAddress()</code>	The session-initiating host address.
<code>\$event.getId()</code>	The session ID.
<code>\$event.getName()</code>	The session name.
<code>\$event.getType().getDescription()</code>	The session state. Three outputs: "STARTED", "FAILED", and "COMPLETED".
<code>\$event.getUser()</code>	The transfer login.

Statement	Description
<code>\$event.GetFiles()</code>	<p>The files that are being transferred. Use this statement in a foreach loop: (Any text after <code>##</code> is a comment)</p> <pre>#foreach (\$file in \$event.GetFiles()) ## \$file is a new variable visible in this foreach loop. ## \$file holds the complete file path and file name. ## \$formatter.decodePath() is used to ensure a correct string decoding. \$formatter.decodePath(\$file) #end</pre> <p>Use the counter <code>\$velocityCount</code> in an if statement to limit the output file count. For example, to list only the first ten files:</p> <pre>#foreach (\$file in \$event.GetFiles()) #if (\$velocityCount &gt; 10) #break #end \$file #end</pre>
<code>\$event.getMessage()</code>	The message that is entered in the email <b>Message</b> field.
<code>\$event.getError()</code>	The error message.

## Time

Statement	Description
<code>\$formatter.date(var, "lang", "format")</code>	<p>Formatting the date and time output. Enter three values in the parenthesis:</p> <ul style="list-style-type: none"> <li><code>var</code> is either <code>\$event.getStartTime()</code> or <code>\$event.getEndTime()</code></li> <li><code>lang</code> is an abbreviated language name; for example, <code>en</code> for English.</li> <li><code>format</code> is the display format. Use these symbols: <ul style="list-style-type: none"> <li><code>yyyy</code> The year; for example, 2010.</li> <li><code>MM</code> Month of the year; for example, 03.</li> <li><code>dd</code> Day of the month; for example, 26.</li> <li><code>HH</code> Hour of the day; for example, 16.</li> <li><code>mm</code> Minute.</li> <li><code>ss</code> Second.</li> <li><code>z</code> Time zone.</li> <li><code>EEE</code> The abbreviated weekday name; for example, <code>Fri</code>.</li> </ul> </li> </ul> <p>For example,</p> <pre>"EEE, yyyy-MM-dd HH:mm:ss z"</pre> <p>shows <code>Fri, 2010-03-26 16:19:01 PST</code>.</p>
<code>\$event.getStartTime()</code>	The session start time.
<code>\$event.getEndTime()</code>	The session end time.

## Statistics

Statement	Description
<code>\$event.getSourceFileCount()</code>	The number of source files.
<code>\$event.getCompletedFileCount()</code>	The number of files that successfully transferred.
<code>\$event.getFailedFileCount()</code>	The number of files that failed to transfer.
<code>\$event.getAverageRatePercentage()</code>	The average transfer rate in bps. Enclose this statement with <code>\$formatter.formatRate()</code> to simplify the output.
<code>\$event.getAverageLossPercentage()</code>	The average packet loss percentage.
<code>\$event.getSourceSizeB()</code>	The source file size. Enclose this statement with <code>\$formatter.toBestUnit()</code> to simplify the output.
<code>\$event.getTransferredB()</code>	The transferred file size. Enclose this statement with <code>\$formatter.toBestUnit()</code> to simplify the output.
<code>\$event.getWrittenB()</code>	The destination file size. Enclose this statement with <code>\$formatter.toBestUnit()</code> to simplify the output.

9. Click **OK** to save your changes.


Apply the notifications to a specific connection host or a transfer session. You can also customize the subject line of the notification emails. For details, see [Using Transfer Notifications](#) on page 48.

## Using Transfer Notifications

Transfer notifications can be sent upon transfer start, complete, and error. Follow these instructions to select and apply them to your transfer sessions:

1. Preview mail templates.

Preview existing templates to decide which one to use. In the application, click **Tools > Mail Templates** to


open the **Mail Template** window. Select an existing template and click . In the **Edit Template** window, click **Preview** to view the template's output example. For instructions on how to create a new template or edit an existing one, see [Configuring Transfer Notifications](#) on page 42.

2. Enable email notifications for connections.

To configure which emails will be sent to specified recipients on specified events, click **Connections** on the main page of the application, select the connection, and select the **Tracking** tab. Select **Send email notifications**, which enables you to do the following:

Item	Description
When	Check the events for which to send notifications.
Subject	Customize the subject line, which can use the same template fields as described in <a href="#">Configuring Transfer Notifications</a> on page 42.
To	Enter the recipients, comma separated.
Template	Select a mail template.
Message	Optionally enter a message to include in the notifications.






Click **OK** to save your changes.

3. Set up notifications for transfers.

Email notifications can also be applied to transfer sessions. In the file browser of the application, right click the file or directory and click **Upload** or **Download**. Go to the **Tracking** tab and select **Send email notifications**. Refer to the previous section for information on the settings.



## ascp: Transferring from the Command Line

---

### Ascp Command Reference

---

The `ascp` executable is a command-line FASP transfer program. This reference describes `ascp` syntax and command options, and the supported environment variables.

For examples of `ascp` commands, see the following topics:

- [Ascp General Examples](#) on page 64
- [Ascp File Manipulation Examples](#) on page 66
- [Ascp Transfers with Object Storage and HDFS](#) on page 67

Another command-line FASP transfer program, A4 (`ascp4`), is optimized for transfers of many small files. It has many of the same capabilities as `ascp`, as well as its own features. For more information, see [Introduction to Ascp4](#) on page 91 and [Comparison of Ascp and Ascp4 Options](#) on page 85.

#### Ascp Syntax

```
ascp options [[username@]src_host:]source1[ source2 ...]
           [[username@]dest_host:]dest_path
```

#### *username*

The username of the Aspera transfer user can be specified as part of the source or destination, whichever is the remote server. It can also be specified with the `--user` option. If you do not specify a username for the transfer, the local username is authenticated by default.

**Note:** If you are authenticating on a Windows computer as a domain user, the transfer server strips the domain from the username. For example, Administrator is authenticated rather than DOMAIN\Administrator. For this reason, you must specify the domain explicitly.

***src\_host***

The name or IP address of the computer where the files or directories to be transferred reside.

***source***

The file or directory to be transferred. Separate multiple arguments with spaces.

***dest\_host***

The name or IP address of the computer where the source files or directories are to be transferred.

***dest\_path***

The destination directory where the source files or directories are to be transferred.

- If the source is a single file, the destination can be a filename. However, if there are multiple source arguments, the destination must be a directory.
- To transfer to the transfer user's docroot, specify "." as the destination.
- If the destination is a symbolic link, then the file is written to the target of the symbolic link. However, if the symbolic link path is a relative path to a file (not a directory) and a partial file name suffix is configured on the receiver, then the destination path is relative to the user's home directory. Files within directories that are sent to symbolic links that use relative paths are not affected.

### Specifying Files, Directories, and Paths

- Specify paths on the remote computer relative to the transfer user's docroot. If the user has a restriction instead of a docroot, specify the full path, which must be allowed by the restriction.
- Avoid the following characters in file and directory names: / \ " : ' ? > < & \* |
- Specify paths with forward-slashes, regardless of the operating system.
- If directory or file arguments contain special characters, specify arguments with single-quotes (') to avoid interpretation by the shell.

**URI paths:** URI paths are supported, but with the following restrictions:

- If the source paths are URIs, they must all be in the same cloud storage account. No docroot (download), local docroot (upload), or source prefix can be specified.
- If a destination path is a URI, no docroot (upload) or local docroot (download) can be specified.
- The special schemes `stdio://` and `stdio-tar://` are supported on the client side only. They cannot be used for specifying an upload destination or download source.
- If required, specify the URI passphrase as part of the URI or set it as an environment variable (`ASPERA_SRC_PASS` or `ASPERA_DST_PASS`, depending on the transfer direction).

**UNC paths:** If the server is Windows and the path on the server is a UNC path (a path that points to a shared directory or file on Windows), it can be specified in an `ascp` command using one of the following conventions:

- As an UNC path that uses backslashes (\): If the client side is a Windows computer, the UNC path can be used with no alteration. For example, `\\192.168.0.10\temp`. If the client is not a Windows computer, every backslash in the UNC path must be replaced with two backslashes. For example, `\\\\192.168.0.10\\temp`.
- As an UNC path that uses forward slashes (/): Replace each backslash in the UNC path with a forward slash. For example, if the UNC path is `\\192.168.0.10\temp`, change it to `//192.168.0.10/temp`. This format can be used with any client-side operating system.

**Testing paths:** To test `ascp` transfers, use a `faux://` argument in place of the source or target path to send random data without writing it to disk at the destination. For more information, see [Testing and Optimizing Transfer Performance](#) on page 100. For examples, see [Ascp General Examples](#) on page 64.

## Environment Variables

The following environment variables can be used with the `ascp` command:

**ASPERA\_DST\_PASS=***password*

The password to authenticate a URI destination.

**ASPERA\_PROXY\_PASS=***proxy\_server\_password*

The password for an Aspera Proxy server.

**ASPERA\_SCP\_COOKIE=***cookie*

A cookie string that you want associated with transfers.

**ASPERA\_SCP\_DOCROOT=***docroot*

The transfer user docroot. Equivalent to using `--apply-local-docroot` when a docroot is set in `aspera.conf`.

**ASPERA\_SCP\_FILEPASS=***password*

The passphrase to be used to encrypt or decrypt files. For use with `--file-crypt`.

**ASPERA\_SCP\_KEY="-----BEGIN RSA PRIVATE KEY..."**

The transfer user private key. Use instead of the `-i` option.

**ASPERA\_SCP\_PASS=***password*

The password for the transfer user.

**ASPERA\_SCP\_TOKEN=***token*

The transfer user authorization token. Overridden by `-W`.

**ASPERA\_SRC\_PASS=***password*

The password to authenticate to a URI source.

## Ascp Options

**-6**

Enable IPv6 address support. When specifying an IPv6 numeric host for `src_host` or `dest_host`, write it in brackets. For example, `username@[2001:0:4137:9e50:201b:63d3:ba92:da]:/path` or `--host=[fe80::21b:21ff:fe1c:5072%eth1]`.

**-@ range\_start:range\_end**

Transfer only part of a file: `range_start` is the first byte to send, and `range_end` is the last. If either position is unspecified, the file's first and last bytes (respectively) are assumed. This option only works for downloads of a single file and does not support transfer resume.

**-A, --version**

Display version and license information.

**--apply-local-docroot**

Apply the local docroot that is set in `aspera.conf` for the transfer user. Use to avoid entering object storage access credentials in the command line. This option is equivalent to setting the environment variable `ASPERA_SCP_DOCROOT`.

**-C nodeid:nodecount**

Enable multi-session transfers (also known as parallel transfers) on a multi-node/multi-core system. A node ID (`nodeid`) and count (`nodecount`) are required for each session. `nodeid` and `nodecount` can be 1-128, but `nodeid` must be less than or equal to `nodecount`, such as 1:2, 2:2. Each session must use a different UDP port specified with the `-O` option. Large files can be split across sessions, see `--multi-session-threshold`. For more information, see the [Enterprise Server Admin Guide: Configuring Multi-Session Transfers](#).

**-c {aes128|aes192|aes256|none}**

Encrypt in-transit file data using the specified cipher. This option overrides the `<encryption_cipher>` setting in `aspera.conf`.

**--check-sshfp=*fingerprint***

Compare *fingerprint* to the server SSH host key fingerprint that is set with `<ssh_host_key_fingerprint>` in `aspera.conf`. Aspera fingerprint convention is to use a hex string without the colons; for example, `f74e5de9ed0d62feaf0616ed1e851133c42a0082`. For more information on SSH host key fingerprints, see the [Enterprise Server Admin Guide: Securing your SSH Server](#).

**Note:** If HTTP fallback is enabled and the transfer "falls back" to HTTP, this option enforces server SSL certificate validation (HTTPS). Validation fails if the server has a self-signed certificate; a properly signed certificate is required.

**-D | -DD | -DDD**

Log at the specified debug level. With each `D`, an additional level of debugging information is written to the log.

**-d**

Create the destination directory if it does not already exist. This option is applied automatically to uploads to object storage.

**--delete-before-transfer**

Before transfer, delete any files that exist at the destination but not also at the source. Do not use with multiple sources, keepalive, URI storage, or HTTP fallback. The `asdelete` tool provides the same capability.

**--dest64**

Indicate that the destination path or URI is base64 encoded.

**-E *pattern***

Exclude files or directories from the transfer based on the specified pattern. Use the `-N` option (include) to specify exceptions to `-E` rules. Rules are applied in the order in which they are encountered, from left to right. The following symbols can be used in the pattern:

- `*` (asterisk) represents zero or more characters in a string, for example `*.tmp` matches `.tmp` and `abcde.tmp`.
- `?` (question mark) represents a single character, for example `t?p` matches `tmp` but not `temp`.

For details and examples, see [Applying Filters to Include and Exclude Files](#) on page 76.

**Note:** When filtering rules are found in `aspera.conf`, they are applied *before* rules given on the command line (`-E` and `-N`).

**-e *prepost\_script***

Run the specified pre-post script as an alternate to the default `aspera-prepost` script. Specify the full path to the pre-post script. The purpose of the pre-script is to run custom commands such as shellscripts, perl scripts, Windows batch files, and executable binaries. The custom commands can make use of transfer statistics and other information placed in environment variables. For details on the setup and usage of prepost scripts, see the Enterprise Server Admin guide.

**--exclude-newer-than=*mtime*, --exclude-older-than=*mtime***

Exclude files (but not directories) from the transfer, based on when the file was last modified. Positive *mtime* values are used to express time, in seconds, since the original system time (usually 1970-01-01 00:00:00). Negative *mtime* values (prefixed with `"-"`) are used to express the number of seconds prior to the current time.

**-f *config\_file***

Read Aspera configuration settings from *config\_file* rather than `aspera.conf` (the default).

**--file-checksum=*hash***

Enable checksum reporting for transferred files, where *hash* is the type of checksum to calculate: sha1, md5, sha-512, sha-384, sha-256, or none (the default). For more information about checksum reporting, see *IBM Aspera Enterprise Server Admin Guide: Reporting Checksums*.

**Note:** If the default value is none, the checksum is the type configured on the server, if any.

**--file-encrypt={*encrypt|decrypt*}**

Encrypt files (when sending) or decrypt files (when receiving) for client-side encryption-at-rest (EAR). Encrypted files have the file extension `.aspera-env`. This option requires the encryption/decryption passphrase to be set with the environment variable `ASPERA_SCP_FILEPASS`. If a client-side encrypted file is downloaded with an incorrect password, the download is successful, but the file remains encrypted and still has the file extension `.aspera-env`. For more information on client-side EAR, see [Client-Side Encryption at Rest \(EAR\)](#) on page 84.

**--file-list=*file***

Transfer all source files and directories listed in *file*. Each source item is specified on a separate line. UTF-8 file format is supported. Only the files and directories are transferred. Path information is not preserved at the destination. To read a file list from standard input, use "-" in place of *file*.

For example, if `list.txt` contains the following list of sources:

```
/tmp/code/compute.php
doc_dir
images/iris.png
images/rose.png
```

and the following command is run:

```
$ ascp --file-list=list.txt --mode=send --user=username --
host=ip_addr .
```

then the destination, in this case the the transfer user's docroot, will contain the following:

```
compute.php
doc_dir (and its contents)
iris.png
rose.png
```

Restrictions:

- The command line cannot use the `user@host:source` syntax. Instead, specify this information with the options `--mode`, `--host`, and `--user`.
- Paths specified in the file list cannot use the `user@host:source` syntax.
- Because multiple sources are being transferred, the destination must be a directory.
- Only one `--file-list` or `--file-pair-list` option is allowed per `ascp` session. If multiple lists are specified, only the last one is used.
- Only files and directories specified in the file list are transferred; any sources specified on the command line are ignored.
- If the source paths are URIs, the size of the file list cannot exceed 24 KB.

To create a file list that also specifies destination paths, use `--file-pair-list`.

**--file-manifest={*none|text*}**

Generate a list of all transferred files when set to `text`. Requires `--file-manifest-path` to specify the location of the list. (Default: `none`)

**--file-manifest-path=*directory***

Save the file manifest to the specified location when using `--file-manifest=text`. File manifests must be stored locally. For cloud or other non-local storage, specify a *local* manifest path.

**`--file-manifest-inprogress-suffix=suffix`**

Apply the specified suffix to the file manifest's temporary file. For use with `--file-manifest=text`. (Default suffix: `.aspera-inprogress`)

**`--file-pair-list=file`**

Transfer files and directories listed in *file* to their corresponding destinations. Each source is specified on a separate line, with its destination on the line following it.

Specify destinations relative to the transfer user's docroot. Even if a destination is specified as an absolute path, the resulting path at the destination will still be relative to the docroot. Destination paths specified in the list are created automatically if they do not already exist.

For example, if the file `pairlist.txt` contains the following list of sources and destinations:

```
Dir1
Dir2
my_images/iris.png
project_images/iris.png
/tmp/code/compute.php
/tmp/code/compute.php
/tmp/tests/testfile
testfile2
```

and the following command is run:

```
$ ascp --file-pair-list=pairlist.txt --mode=send --user=username
--host=ip_addr .
```

then the destination, in this case the transfer user's docroot, now contains the following:

```
Dir2 (and its contents)
project_images/iris.png
tmp/code/compute.php
testfile2
```

Restrictions:

- The command line cannot use the `user@host:source` syntax. Instead, specify this information with the options `--mode`, `--host`, and `--user`.
- The `user@host:source` syntax cannot be used with paths specified in the file list.
- Because multiple sources are being transferred, the destination specified on the command line must be a directory.
- Only one `--file-pair-list` or `--file-list` option is allowed per `ascp` session. If multiple lists are specified, only the last one is used.
- Only files from the file pair list are transferred; any additional source files specified on the command line are ignored.
- If the source paths are URIs, the file list cannot exceed 24 KB.

For additional examples, see [Ascp General Examples](#) on page 64.

**`-G write_size`**

If the transfer destination is a server, use the specified write-block size, which is the maximum number of bytes that the receiver can write to disk at a time. Default: 256 KB, Range: up to 500 MB. This option accepts suffixes "M" or "m" for *mega* and "K" or "k" for *kilo*, such that a `write_size` of 1M is one MB.

This is a performance-tuning option that overrides the `write_block_size` set in the client's `aspera.conf`. However, the `-G` setting is overridden by the `write_block_size` set in the server's `aspera.conf`. The receiving server never uses the `write_block_size` set in the client's `aspera.conf`.

**-g *read\_size***

If the transfer source is a server, use the specified read-block size, which is the maximum number of bytes that the sender reads from the source disk at a time. Default: 256 KB, Range: up to 500 MB. This option accepts suffixes "M" or "m" for *mega* and "K" or "k" for *kilo*, such that a `read_size` of 1M is one MB.

This is a performance-tuning option that overrides the `read_block_size` set in the client's `aspera.conf`. However, the `-g` setting is overridden by the `read_block_size` set in the server's `aspera.conf`. When set to the default value, the read size is the default internal buffer size of the server, which might vary by operating system. The sending server never uses the `read_block_size` set in the client's `aspera.conf`.

**-h, --help**

Display the help text.

**--host=*hostname***

Transfer to the specified host name or address. Requires `--mode`. This option can be used instead of specifying the host with the `hostname:file` syntax.

**-i *private\_key\_file***

Authenticate the transfer using public key authentication with the specified SSH private key file. The argument can be just the file name if the private key is located in `user_home_dir/.ssh/`, because `ascp` automatically searches for key files there. Multiple private key files can be specified by repeating the `-i` option. The keys are tried in order and the process ends when a key passes authentication or when all keys have been tried without success, at which point authentication fails.

**-K *probe\_rate***

Measure bottleneck bandwidth at the specified probing rate (Kbps). (Default: 100Kbps)

**-k {0|1|2|3}**

Enable the resuming of partially transferred files at the specified resume level. (Default: 0)

Specify this option for the first transfer or it will not work for subsequent transfers. Resume levels:

- k 0 – Always retransfer the entire file.
- k 1 – Compare file attributes and resume if they match, and retransfer if they do not.
- k 2 – Compare file attributes and the sparse file checksums; resume if they match, and retransfer if they do not.
- k 3 – Compare file attributes and the full file checksums; resume if they match, and retransfer if they do not.

If a complete file exists at the destination (no `.aspx`), the source and destination file sizes are compared. If a partial file and a valid `.aspx` file exist at the destination, the source file size and the file size recorded in the `.aspx` file are compared.

**Note:** If the destination is a URI path, then the only valid options are `-k 0` and `-k 1` and no `.aspx` file is created.

**-L *local\_log\_dir[:size]***

Log to the specified directory on the client computer rather than the default directory. Optionally, set the size of the log file (Default: 10 MB). See also `-R` for setting the log directory on the server.

**-l *max\_rate***

Transfer at rates up to the specified target rate. (Default: 10000 Kbps) This option accepts suffixes "G" or "g" for *giga*, "M" or "m" for *mega*, "K" or "k" for *kilo*, and "P", "p", or "%" for percentage. Decimals are allowed. If this option is not set by the client, the setting in the server's



`aspera.conf` is used. If a rate cap is set in the local or server `aspera.conf`, the rate does not exceed the cap.

**-m *min\_rate***

Attempt to transfer no slower than the specified minimum transfer rate. (Default: 0) If this option is not set by the client, then the server's `aspera.conf` setting is used. If a rate cap is set in the local or server `aspera.conf`, then the rate does not exceed the cap.

**--mode={send|recv}**

Transfer in the specified direction: `send` or `recv` (receive). Requires `--host`.

**--move-after-transfer=*archivedir***

Move source files and copy source directories to *archivedir* after they are successfully transferred. Because directories are copied, the original source tree remains in place. The transfer user must have write permissions to the *archivedir*. The *archivedir* is created if it does not already exist. If the archive directory cannot be created, the transfer proceeds and the source files remain in their original location.

To preserve portions of the file path above the transferred file or directory, use this option with `--src-base`. For an example, see [Ascp File Manipulation Examples](#) on page 66.

To remove empty source directories (except those specified as the source to transfer), use this option with `--remove-empty-directories`.

Restrictions:

- *archivedir* must be on the same file system as the source. If the specified archive is on a separate file system, it is created (if it does not exist), but an error is generated and files are not moved to it.
- For cloud storage, *archivedir* must be in the same cloud storage account as the source and must not already contain files with the same name (the existing files cannot be overwritten and the archiving fails).
- If the source is on a remote system (`ascp` is run in receive mode), *archivedir* is subject to the same docroot restrictions as the remote user.
- `--remove-after-transfer` and `--move-after-transfer` are mutually exclusive. Using both in the same session generates an error.
- Empty directories are not saved to *archivedir*.
- When used with `--remove-empty-directories` and `--src-base`, scanning for empty directories starts at the specified source base and proceeds down any subdirectories. If no source base is specified and a file path (as opposed to a directory path) is specified, then only the immediate parent directory is removed (if empty) after the source files have been moved.

**--multi-session-threshold=*threshold***

Split files across multiple `ascp` sessions if their size is greater than or equal to *threshold*. Use with `-C`, which enables multi-session transfers.

Files whose sizes are less than *threshold* are not split. If *threshold* is set to 0 (the default), no files are split.

If `--multi-session-threshold` is not used, the threshold value is taken from the setting for `<multi_session_threshold_default>` in the `aspera.conf` file on the client. If not found in `aspera.conf` on the client, the setting is taken from `aspera.conf` on the server. The command-line setting overrides any `aspera.conf` settings, including when the command-line setting is 0 (zero).

Multi-session uploads to cloud storage are supported for S3 only and require additional configuration. For more information, see the [Enterprise Server Admin Guide: Configuring Multi-Session Transfers](#).

**-N *pattern***

Protect ("include") files or directories from exclusion by any `-E` (exclude) options that follow it. Files and directories are specified using *pattern*. Each option-plus-pattern is a *rule*. Rules are applied in the order (left to right) in which they're encountered. Thus, `-N` rules protect files only from `-E` rules that follow them. Create patterns using standard globbing wildcards and special characters such as the following:

- `*` (asterisk) represents zero or more characters in a string, for example `*.tmp` matches `.tmp` and `abcde.tmp`.
- `?` (question mark) represents any single character, for example `t?p` matches `tmp` but not `temp`.

For details on specifying patterns and rules, including examples, see [Applying Filters to Include and Exclude Files](#) on page 76.

**Note:** Filtering rules can also be specified in `aspera.conf`. Rules found in `aspera.conf` are applied *before* any `-E` and `-N` rules specified on the command line.

### `-O fasp_port`

Use the specified UDP port for FASP transfers. (Default: 33001)

### `--overwrite={never|always|diff|diff+older|older}`

Overwrite destination files with source files of the same name. Default: `diff`. This option takes the following values:

#### **never**

Never overwrite the file. However, if the parent folder is not empty, its access, modify, and change times may still be updated.

#### **always**

Always overwrite the file.

#### **diff**

Overwrite the file if different from the source. If a complete file at the destination is the same as a file on the source, it is not overwritten. Partial files are overwritten or resumed depending on the resume policy.

#### **diff+older**

Overwrite the file if older and also different than the source. For example, if the destination file is the same as the source, but with a different timestamp, it will not be overwritten. Plus, if the destination file is different than the source, but newer, it will not be overwritten.

#### **older**

Overwrite the file if its timestamp is older than the source timestamp.

**Interaction with resume policy (-k):** If the overwrite method is `diff` or `diff+older`, difference is determined by the resume policy (`-k {0|1|2|3}`). If `-k 0` or no `-k` is specified, the source and destination files are always considered different and the destination file is always overwritten. If `-k 1`, the source and destination files are compared based on file attributes (currently file size). If `-k 2`, the source and destination files are compared based on sparse checksums. If `-k 3`, the source and destination files are compared based on full checksums.

### `-P ssh-port`

Use the specified TCP port to initiate the FASP session. (Default: 22)

### `-p`

Preserve file timestamps for access and modification time. Equivalent to setting `--preserve-modification-time`, `--preserve-access-time`, and `--preserve-creation-time`. Timestamp support in object storage varies by provider; consult your object storage documentation to determine which settings are supported.

On Windows, modification time may be affected when the system automatically adjusts for Daylight Savings Time (DST). For details, see the Microsoft KB article, <http://support.microsoft.com/kb/129574>.

On Isilon IQ OneFS systems, access time (`atime`) is disabled by default. In this case, `atime` is the same as `mtime`. To enable the preservation of `atime`, run the following command:

```
# sysctl efs.bam.atime_enabled=1
```

#### **--partial-file-suffix=suffix**

Enable the use of partial files for files that are in transit, and set the suffix to add to names of partial files. (The suffix does not include a " . ", as for a file extension, unless explicitly specified as part of the suffix.) This option only takes effect when set on the receiver side. When the transfer is complete, the suffix is removed. (Default: suffix is null; use of partial files is disabled.)

#### **--policy={high|fair|low|fixed}**

Set the FASP transfer policy.

##### **high**

Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, the transfer rate is twice as fast as a fair-policy transfer. The `high` policy requires maximum (target) and minimum transfer rates.

##### **fair**

Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, bandwidth is shared fairly by transferring at an even rate. The `fair` policy requires maximum (target) and minimum transfer rates.

##### **low**

Adjust the transfer rate to use the available bandwidth up to the maximum rate. Similar to fair mode, but less aggressive when sharing bandwidth with other network traffic. When congestion occurs, the transfer rate is reduced to the minimum rate until other traffic decreases.

##### **fixed**

Attempt to transfer at the specified target rate, regardless of network or storage capacity. This can decrease transfer performance and cause problems on the target storage. Aspera discourages using the `fixed` policy except in specific contexts, such as bandwidth testing. The `fixed` policy requires a maximum (target) rate.

If `--policy` is not set, `ascp` uses the server-side policy setting (`fair` by default). If the server does not allow the selected policy, the transfer fails.

#### **--precalculate-job-size**

Calculate the total size before starting the transfer. The server-side `pre_calculate_job_size` setting in `aspera.conf` overrides this option.

#### **--preserve-access-time**

Preserve the source-file access timestamps at the destination. Because source access times are updated by the transfer operation, the timestamp preserved is the one just *prior* to the transfer. (To prevent access times at the source from being updated by the transfer operation, use the `--preserve-source-access-time` option.)

On Isilon IQ OneFS systems, access time (`atime`) is disabled by default. In this case, `atime` is the same as `mtime`. To enable the preservation of `atime`, run the following command:

```
# sysctl efs.bam.atime_enabled=1
```

#### **--preserve-acls=mode, --remote-preserve-acls=mode**

#### **--preserve-xattrs=mode, --remote-preserve-xattrs=mode**

Preserve a file's access control lists (ACLs) and/or extended attributes (xattrs) when transferring between different file system types. `--preserve-acls` cannot preserve NFSv4 ACLs that are used by Spectrum Scale (formerly GPFS) filesystems.

The storage *mode* can be one of the following:

#### **native**

Preserve attributes using the native capabilities of the file system. However, *native* mode is not supported on all file systems; `--preserve-acls=native` and `--remote-preserve-acls=nativework` only on Windows computers, and `--preserve-xattrs=native` and `--remote-preserve-xattrs=native` work only on Linux computers.

#### **metafile**

Preserve attributes in a separate file, named *filename.aspera-meta*. For example, attributes for *readme.txt* are preserved in a second file named *readme.txt.aspera-meta*. The metafiles are platform independent and can be copied between hosts without loss of information. The *metafile* mode is supported on all file systems.

#### **none**

Do not preserve attributes (default).

If the client and server have different values for *mode*, *metafile* is used silently. Metafiles are overwritten by subsequent transfers if `--overwrite` is set to any value other than *never*.

The `remote-` options specify the storage mode to use on the remote file system. If this option is not specified, the mode will be whatever is specified for the local file system. A `remote-` option with mode set to *native* may be overridden by the remote *ascp* if *native* mode is unsupported on the remote file system.

The amount of attribute data per file that can be transferred successfully is subject to *ascp*'s internal PDPU size limitation.

Note that older versions of *ascp* do not support values other than *none*, and transfers using *native* or *metafile* fail with an error that reports incompatible FASP protocol versions.

#### **--preserve-creation-time**

(Windows only) Preserve source-file creation timestamps at the destination. Only Windows systems retain information about creation time. If the destination is not a Windows computer, this option is ignored.

#### **--preserve-file-owner-gid, --preserve-file-owner-uid**

(Linux, UNIX, and macOS only) Preserve the group information (*gid*) or owner information (*uid*) of the transferred files. These options require the transfer user to be authenticated as a superuser.

#### **--preserve-modification-time**

Set the modification time, the last time a file or directory was modified (written), of a transferred file to the modification of the source file or directory. Preserve source-file modification timestamps at the destination.

On Windows, modification time may be affected when the system automatically adjusts for Daylight Savings Time (DST). For details, see the Microsoft KB article, <http://support.microsoft.com/kb/129574>.

#### **--preserve-source-access-time**

Preserve the access times of the original sources to the last access times prior to transfer. This prevents access times at the source from being updated by the transfer operation. Typically used in conjunction with the `--preserve-access-time` option.

#### **--preserve-xattrs={native|metafile|none}**

Preserve a file's extended attributes (xattrs) when transferring between different file system types. *mode* can be *native*, *metafile*, or *none* (default). See `--preserve-acls` for a full description of *mode* and the behavior of this option.

**--proxy=proxy\_url**

Use the proxy server at the specified address. *proxy\_url* should be specified with the following syntax:

```
dnat[s]://proxy_username:proxy_password@server_ip_address:port
```

The default ports for DNAT and DNATS protocols are 9091 and 9092. For a usage example, see [Ascp General Examples](#) on page 64.

**-q**

Run `ascp` in quiet mode (disables the progress display).

**-R remote\_log\_dir**

Log to the specified directory on the server rather than the default directory. **Note:** Client users restricted to `aspsell` are not allowed to use this option. To specify the location of the local log, use `-L`.

**--remote-preserve-acls={native|metafile|none}**

Preserve a file's access control lists (ACLs) when transferring between different file system types. *mode* can be *native*, *metafile*, or *none* (default). See `--preserve-acls` for a full description of *mode* and the behavior of this option.

**--remote-preserve-xattrs={native|metafile|none}**

Preserve a file's extended attributes (xattrs) when transferring between different file system types. *mode* can be *native*, *metafile*, or *none* (default). See `--preserve-acls` for a full description of *mode* and the behavior of this option.

**--remove-after-transfer**

Remove all source files, but not the source directories, once the transfer has completed successfully. Requires write permissions on the source.

**--remove-empty-directories**

Remove empty source directories once the transfer has completed successfully, but do not remove a directory specified as the source argument. To also remove the specified source directory, use `--remove-empty-source-directory`. Directories can be emptied using `--move-after-transfer` or `--remove-after-transfer`. Scanning for empty directories starts at the `srcbase` and proceeds down any subdirectories. If no source base is specified and a file path (as opposed to a directory path) is specified, then only the immediate parent directory is scanned and removed if it's empty following the move of the source file. **Note:** Do not use this option if multiple processes (`ascp` or other) might access the source directory at the same time.

**--remove-empty-source-directory**

Remove directories specified as the source arguments. For use with `--remove-empty-directories`.

**-S remote\_ascp**

Use the specified remote `ascp` binary, if different than `ascp`.

**--save-before-overwrite**

Save a copy of a file before it is overwritten by the transfer. A copy of `filename.ext` is saved as `filename.yyyy.mm.dd.hh.mm.ss.index.ext` in the same directory. *index* is set to 1 at the start of each second and incremented for each additional file saved during that second. The saved copies retain the attributes of the original. Not supported for URI path destinations.

**--skip-special-files**

Skip special files, such as devices and pipes, without reporting errors for them.

**--source-prefix=prefix**

Prepend *prefix* to each source path. The prefix can be a conventional path or a URI; however, URI paths can be used only if no docroot is defined.

**--source-prefix64=prefix**

Prepend the base64-encoded *prefix* to each source path. If `--source-prefix=prefix` is also used, the last option takes precedence.

**--src-base=prefix**

Strip the specified path prefix from the source path of each transferred file or directory. The remaining portion of the path remains intact at the destination.

Without `--src-base`, source files and directories are transferred without their source path. (However, directories do include their contents.)

Example: To transfer the folders and files in the `/clips/out` folder, but not the `out` folder itself, run the following command:

```
$ ascp -d --src-base=/clips/out/ /clips/out/ root@10.0.0.1:/in
```

Result: At the destination, the source folders and files appear in the `in` directory:

Source	Destination (docroot)	Destination without <code>--src-base</code>
<code>/clips/out/file1</code>	<code>/in/file1</code>	<code>/in/out/file1</code>
<code>/clips/out/folderA/file2</code>	<code>/in/folderA/file2</code>	<code>/in/out/folderA/file2</code>
<code>/clips/out/folderB/file3</code>	<code>/in/folderB/file3</code>	<code>/in/out/folderB/file3</code>

**Note:** Sources located outside the source base are not transferred. No errors or warnings are issued, but the skipped files are logged. For example, if `/clips/file4` were included in the above example sources, it would not be transferred because it is located outside the specified source base, `/clips/out/`.

**Use with URIs:** The `--src-base` option performs a character-to-character match with the source path. For object storage source paths, the prefix must specify the URI in the same manner as the source paths. For example, if a source path includes an embedded passphrase, the prefix must also include the embedded passphrase otherwise it will not match.

For additional examples, see [Ascp File Manipulation Examples](#) on page 66.

**--symbolic-links={follow|copy|copy+force|skip}**

Handle symbolic links using the specified method, as allowed by the server. For more information on symbolic link handling, see [Symbolic Link Handling](#) on page 81. On Windows, the only method is `skip`. On other operating systems, any of the following methods can be used:

**follow**

Follow symbolic links and transfer the linked files. (Default)

**copy**

Copy only the alias file. If a file with the same name is found at the destination, the symbolic link is not copied.

**copy+force**

Copy only the alias file. If a file (not a directory) with the same name is found at the destination, the alias replaces the file. If the destination is a symbolic link to a directory, it's not replaced.

**skip**

Skip symbolic links. Do not copy the link or the file it points to.

**-T**

Disable in-transit encryption for maximum throughput.

**-u *user\_string***

Define a user string, such as variables, for pre- and post-processing. This string is passed to the pre- and post-processing scripts as the environment variable `$USERSTR`.

**--user=*username***

Authenticate the transfer using the specified username. Use this option instead of specifying the username as part of the destination path (as *user@host:file*).

**Note:** If you are authenticating on a Windows computer as a domain user, the transfer server strips the domain from the username. For example, `Administrator` is authenticated rather than `DOMAIN\Administrator`. For this reason, you must specify the domain explicitly.

**-v**

Run `ascp` in verbose mode. This option prints connection and authentication debug messages in the log file. For information on log files, see [Log Files](#) on page 102 .

**-w {*token\_string*[@*token\_file*]}**

Authenticate using the authorization token string for the transfer, either as the string itself or when preceded with an `@`, the full path to the token file. This option takes precedence over the setting for the `ASPERA_SCP_TOKEN` environment variable.

**-wr, -wf**

Measure and report bandwidth from server to client (`-wr`) or client to server (`-wf`) before the transfer.

**-X *remsg\_size***

Limit the size of retransmission requests to no larger than the specified size, in bytes. (Max: 1440)

**-Z *dgram\_size***

Use the specified datagram size (MTU) for FASP transfers. Range: 296-65535 bytes. (Default: the detected path MTU)

As of v3.3, datagram size can be specified on the server by setting `<datagram_size>` in `aspera.conf`. The server setting overrides the client setting, unless the client is using a version of `ascp` that is older than 3.3, in which case the client setting is used. If the pre-3.3 client does not set `-Z`, the datagram size is the discovered MTU and the server logs the message "LOG Peer client does not support alternative datagram size".

### Ascp Options for HTTP Fallback

**-I *cert\_file***

Certify fallback transfers with the specified HTTPS certificate file.

**-j {0|1}**

Encode all HTTP transfers as JPEG files when set to 1. (Default: 0)

**-t *port***

Transfer via the specified server port for HTTP fallback.

**-x *proxy\_server***

Transfer to the specified proxy server address for HTTP fallback.

**-Y *key\_file***

Cerify HTTPS fallback transfers using the specified HTTPS transfer key.

**-y {0|1}**

If set to "1", use the HTTP fallback transfer server when a UDP connection fails. (Default: 0)

## Ascp General Examples

The following are examples of initiating FASP file transfers using the `ascp` command.

To describe filepaths, use single-quote (') and forward-slashes (/) on all platforms. Avoid the following characters in filenames: / \ " : ' ? > < & \* |

- **Fair-policy transfer**

Fair-policy transfer with maximum rate 100 Mbps and minimum at 1 Mbps, without encryption, transfer all files in `\local-dir\files` to 10.0.0.2:

```
$ ascp --policy=fair -l 100m -m 1m /local-dir/files root@10.0.0.2:/remote-dir
```

- **Fixed-policy transfer**

Fixed-policy transfer with target rate 100 Mbps, without encryption, transfer all files in `\local-dir\files` to 10.0.0.2:

```
$ ascp -l 100m /local-dir/files root@10.0.0.2:/remote-dir
```

- **Specify UDP port for transfer**

Perform a transfer with UDP port 42000:

```
$ ascp -l 100m -O 42000 /local-dir/files user@10.0.0.2:/remote-dir
```

- **Public key authentication**

Transfer with public key authentication using key file `<home dir>/.ssh/aspera_user_1-key` local-dir/files:

```
$ ascp -l 10m -i ~/.ssh/aspera_user_1-key local-dir/files root@10.0.0.2:/remote-dir
```

- **Username or filepath contains a space**

Enclose the target in double-quotes when spaces are present in the username and remote path:

```
$ ascp -l 100m local-dir/files "User Name@10.0.0.2:/remote directory"
```

- **Content is specified in a file pair list**

Specify source content to transfer to various destinations in a file pair list. Source content is specified using the full file or directory path. Destination directories are specified relative to the transfer user's docroot, which is specified as "." at the end of the `ascp` command. For example, the following is a simple file pair list, `filepairlist.txt` that lists two source folders, `folder1` and `folder2`, with two destinations, `tmp1` and `tmp2`:

```
/tmp/folder1
tmp1
/tmp/folder2
tmp2
```

```
$ ascp --user=user_1 --host=10.0.0.2 --mode=send --file-pair-list=/tmp/
filepairlist.txt .
```

This command and file pair list create the following directories within the transfer user's docroot on the destination:

```
/tmp1/folder1
/tmp2/folder2
```

- **Network shared location transfer**



Send files to a network shares location `\\1.2.3.4\nw-share-dir`, through the computer `10.0.0.2`:

```
$ ascp local-dir/files root@10.0.0.2:"//1.2.3.4/nw-share-dir/"
```

- **Parallel transfer on a multicore system**

Use parallel transfer on a dual-core system, together transferring at the rate 200Mbps, using UDP ports 33001 and 33002. Two commands are executed in different Terminal windows:

```
$ ascp -C 1:2 -O 33001 -l 100m /file root@10.0.0.2:/remote-dir &
$ ascp -C 2:2 -O 33002 -l 100m /file root@10.0.0.2:/remote-dir
```

- **Upload with content protection**

Upload the file `local-dir/file` to the server `10.0.0.2` with password protection (password: `secRet`):

```
$ export ASPERA_SCP_FILEPASS=secRet ascp -l 10m --file-crypt=encrypt local-dir/file
root@10.0.0.2:/remote-dir/
```

The file is saved on the server as `file.aspera-env`, with the extension indicating that the file is encrypted. See the next example for how to download and decrypt an encrypted file from the server.

- **Download with content protection and decryption**

Download an encrypted file, `file.aspera-env`, from the server `10.0.0.2` and decrypt while transferring:

```
$ export ASPERA_SCP_FILEPASS=secRet; ascp -l 10m --file-crypt=decrypt root@10.0.0.2:/remote-
dir/file.aspera-env /local-dir
```

- **Decrypt a downloaded, encrypted file**

If the password-protected file `file1` is downloaded on the local computer without decrypting, decrypt `file1.aspera-env` (the name of the downloaded/encrypted version of `file1`) to `file1`:

```
$ export ASPERA_SCP_FILEPASS=secRet; /Library/Aspera/bin/asunprotect -o file1 file1.aspera-
env
```

- **Download through Aspera forward proxy with proxy authentication**

User `Pat` transfers the file `/data/file1` to `/Pat_data/` on `10.0.0.2`, through the proxy server at `10.0.0.7` with the proxy username `aspera_proxy` and password `pa33w0rd`. After running the command, `Pat` is prompted for the `ascp` password.

```
$ ascp --proxy dnats://aspera_proxy:pa33w0rd@10.0.0.7 /data/file1 Pat@10.0.0.2:/Pat_data/
```

### Test transfers using `faux`://

For information on the syntax, see [Testing and Optimizing Transfer Performance](#) on page 100.

- **Transfer random data (no source storage required)**

Transfer 20 GB of random data as user `root` to file `newfile` in the directory `/remote-dir` on `10.0.0.2`:

```
$ascp --mode=send --user=root --host=10.0.0.2 faux:///newfile?20g /remote-dir
```

- **Transfer a file but do not save results to disk (no destination storage required)**

Transfer the file `/tmp/sample` as user `root` to `10.0.0.2`, but do not save results to disk:

```
$ascp --mode=send --user=root --host=10.0.0.2 /tmp/sample faux://
```

- **Transfer random data and do not save result to disk (no source or destination storage required)**

Transfer 10 MB of random data from `10.0.0.2` as user `root` and do not save result to disk:

```
$ascp --mode=send --user=root --host=10.0.0.2 faux:///dummy?10m faux://
```

## Ascp File Manipulation Examples

Below are examples of using the `ascp` command to manipulate files. In each example, the client is the local computer and the server is the remote computer.

- **Upload a directory**

Upload the directory `/data/` to the server at `10.0.0.1`, and place it in the `/storage/` directory on the server:

```
$ ascp /src/data/ root@10.0.0.1:/storage/
```

- **Upload only the contents of a directory (not the directory itself) by using the `--src-base` option:**

Upload only the contents of `/data/` to the `/storage/` directory at the destination. Strip the `/src/data/` portion of the source path and preserve the remainder of the file structure at the destination:

```
$ ascp --src-base=/src/data/ /src/data/ root@10.0.0.1:/storage/
```

- **Upload a directory and its contents to a new directory by using the `-d` option.**

Upload the `/data/` directory to the server and if it doesn't already exist, create the new folder `/storage2/` to contain it, resulting in `/storage2/data/` at the destination.

```
$ ascp -d /src/data/ root@10.0.0.1:/storage2/
```

- **Upload the contents of a directory, but not the directory itself, by using the `--src-base` option:**

Upload all folders and files in the `/clips/out/` folder, but not the `out/` folder itself, to the `/in/` folder at the destination.

```
$ ascp -d --src-base=/clips/out/ /clips/out/ root@10.0.0.1:/in/
```

Result: The source folders and their content appear in the `in` directory at the destination:

Source	Destination (docroot)	Destination without <code>--src-base</code>
<code>/clips/out/file1</code>	<code>/in/file1</code>	<code>/in/out/file1</code>
<code>/clips/out/folderA/file2</code>	<code>/in/folderA/file2</code>	<code>/in/out/folderA/file2</code>
<code>/clips/out/folderB/file3</code>	<code>/in/folderB/file3</code>	<code>/in/out/folderB/file3</code>

Without `--src-base`, the example command transfers not only the contents of the `out/` folder, but the folder itself.

- **Upload only the contents of a file and a directory to a new directory by using `--src-base`**

Upload a file, `/monday/file1`, and a directory, `/tuesday/*`, to the `/storage/` directory on the server, while stripping the `srcbase` path and preserving the rest of the file structure. The content is saved as `/storage/monday/file1` and `/storage/tuesday/*` on the server.

```
$ ascp --src-base=/data/content /data/content/monday/file1 /data/content/tuesday/ root@10.0.0.1:/storage
```

- **Download only the contents of a file and a directory to a new directory by using `--src-base`**

Download a file, `/monday/file1`, and a directory, `/tuesday/*`, from the server, while stripping the `srcbase` path and preserving the rest of the file structure. The content is saved as `/data/monday/file1` and `/data/tuesday/*` on the client.

```
$ ascp --src-base=/storage/content root@10.0.0.1:/storage/content/monday/file1 root@10.0.0.1:/storage/content/tuesday/ /data
```

- **Move the source file on the client after it is uploaded to the server by using `--move-after-transfer`**

Upload `file0012` to Pat's docroot on the server at 10.0.0.1, and move (not copy) the file from `C:/Users/Pat/srcdir/` to `C:/Users/Pat/Archive` on the client.

```
$ ascp --move-after-transfer=C:/Users/Pat/Archive C:/Users/Pat/srcdir/
file0012 Pat@10.0.0.1:/
```

- **Move the source file on the server after it is downloaded to the client by using `--move-after-transfer`**

Download `srcdir` from the server to `C:/Users/Pat` on the client, and move (not copy) `srcdir` to the archive directory `/Archive` on the server.

```
$ ascp --move-after-transfer=Archive Pat@10.0.0.1:/srcdir C:/Users/Pat
```

- **Move the source file on the client after it is uploaded to the server and preserve the file structure one level above it by using `--src-base` and `--move-after-transfer`**

Upload `file0012` to Pat's docroot on the server at 10.0.0.1, and save it as `/srcdir/file0012` (stripped of `C:/Users/Pat`). Also move `file0012` from `C:/Users/Pat/srcdir/` to `C:/Users/Pat/Archive` on the client, where it is saved as `C:/Users/Pat/Archive/srcdir/file0012`.

```
$ ascp --src-base=C:/Users/Pat --move-after-transfer=C:/Users/Pat/Archive
C:/Users/Pat/srcdir/file0012 Pat@10.0.0.1:/
```

- **Delete a local directory once it is uploaded to the remote server by using `--remove-after-transfer` and `--remove-empty-directories`**

Upload `/content/` to the server, then delete its contents (excluding partial files) and any empty directories on the client.

```
$ ascp -k2 -E "*.partial" --remove-after-transfer --remove-empty-
directories /data/content root@10.0.0.1:/storage
```

- **Delete a local directory once its contents have been transferred to the remote server by using `--src-base`, `--remove-after-transfer`, and `--remove-empty-directories`**

Upload `/content/` to the server, while stripping the `srcbase` path and preserving the rest of the file structure. The content is saved as `/storage/*` on the server. On the client, the contents of `/content/`, including empty directories but excluding partial files, are deleted.

```
$ ascp -k2 -E "*.partial" --src-base=/data/content --remove-after-transfer
--remove-empty-directories /data/content root@10.0.0.1:/storage
```

## Ascp Transfers with Object Storage and HDFS

---

### Ascp Transfers with ATS and ATCM

Transfers with ATS and ATCM use the `xfer` transfer user who is authenticated with the Aspera Connect private key and authorized to the object storage by a Basic token. The Basic token can be set as the environment variable `ASPERA_SCP_TOKEN` or specified in the command line using `-W "Basic token_string"`.

The following instructions describe how to retrieve and set up the Aspera Connect private key (`aspera_tokenauth_id_rsa`), set a Basic token associated with your ATS or ATCM access key, and compose a command line transfer.

1. Create or retrieve your ATS or ATCM access key.

For instructions, see the [ATS Getting Started Guide: Configuring Aspera Client for Transfers](#) or the [IBM Aspera Transfer Cluster Manager Admin Guide: Creating Access Keys in the Cluster Manager](#).

2. For transfers with ATS, create a Basic authentication token using your Aspera access key and secret key.

Create a basic auth token by base64-encoding the text string `access_key_id:secret`.

```
$ echo -n access_key_id:access_key_secret | base64
```

For example:

```
$ echo -n diDeuFLcpG9IYdsvxj0SCq4mOohNJTKvp5Q2nRWjDgIA:aspera | base64
```

The basic auth token looks similar to the following:

```
ZG1EZxVGTGNwRz1JWWRzdnhqMFNDcTRtT29oTkpUS3ZwNVEyblJXakRnSUE6YXNwZXJh
```

3. For transfers with ATCM, retrieve the authentication token associated with your access key.

On the **Clusters** page, select the cluster, click **Access Keys**, and click **Details** for your access key. Copy the value for **Authentication Token**.

4. Set the token as an environment variable (optional).

Aspera recommends setting the token as an environment variable so that you do not need to specify it in the command line (which can be done by specifying the `-W` option, described in the next step).

```
# export ASPERA_SCP_TOKEN="Basic token_string"
```

For example:

```
# export ASPERA_SCP_TOKEN="Basic
ZDFQbGJaQjN4cHRxS3d2a29hM19TdeopsedoitgxcTRUWi05SmxSTld2SG1RZ1VQZmxZQ0t1QjVWRlFsbXBK
```

5. Transfer with your object storage.

The following is the upload syntax if the Basic token is set as an environment variable.

```
$ ascp -i /full/path/to/aspera_tokenauth_id_rsa -P 33001 -
l target_rate source_files xfer@server_name:destination_path
```

`-i` sets the path to the Aspera private key, which is:

```
/Library/Aspera/var/aspera_tokenauth_id_rsa
```

The destination path is relative to the docroot specified in the access key (leave blank or set to `"/` to transfer to the root directory).

For example:

```
$ ascp -i /Library/Aspera/var/aspera_tokenauth_id_rsa -P 33001 -l 20m /
Users/aspera/Desktop/Images/image01 xfer@ats-aws-us-us-east-1.aspera.io:/
images
```

If you did not set the token as an environment variable, use `-W`:

```
$ ascp -i /full/path/to/aspera_tokenauth_id_rsa -W "Basic token_string" -P
33001 -l target_rate source_files xfer@server_name:destination_path
```

For example:

```
$ ascp -i /Library/Aspera/var/aspera_tokenauth_id_rsa -W "Basic
ZG1EZxVGTGNwRz1JWWRzdnhqMFNDcTRtT29oTkpUS3ZwNVEyblJXakRnSUE6YXNwZXJh" -
P 33001 -l 200m /Users/aspera/Desktop/Images/image01 xfer@ats-aws-us-us-
east-1.aspera.io:/images
```

## Transfers with Aspera On Demand and Object-Storage-Based Aspera Servers

Transfers with Aspera On Demand servers or Enterprise Servers located in object storage must provide credentials to the object storage in one of the following ways:

- Specify the storage password or secret key in the transfer user's docroot. (Preferred method)
- Set the storage password or secret key as an environment variable.
- Specify the storage password or secret key in the command line.

### With Docroot Configured: Authenticate in the Docroot

If your transfer user account has a docroot set that includes credentials or credentials are configured in the `.properties` file, `ascp` transfers to and from Alibaba Cloud, Amazon S3, IBM COS - S3, Google Cloud Storage, Akamai, Softlayer, Azure, and are the same as regular `ascp` transfers. For command syntax examples, see [Ascp General Examples](#) on page 64.

For instructions on configuring a docroot for these types of storage, see [Aspera Enterprise Server Admin Guide \(Linux\): Docroot Path Formatting for Cloud, Object, and HDFS Storage](#). You are prompted for the transfer user's password upon running these commands unless you have set the `ASPERA_SCP_PASS` environment variable or are using an SSH key, as described previously.

### With No Docroot Configured: Authenticate with Environment Variables

You can set an environment variable (`ASPERA_DEST_PASS`) with the storage password or access key using the command below:

```
$ export ASPERA_DEST_PASS = secret_key
```

With this and `ASPERA_SCP_PASS` set, run `ascp` with the syntax listed in the table above, but you do not need to include the storage password or access key, and are not prompted for the Aspera password upon running the command.

**Note:** The `ASPERA_DEST_PASS` variable is not applicable to Google Cloud Storage or Amazon S3 using IAM roles.

### With No Docroot Configured: Authenticate in the Command Line

If you do not have a docroot configured and do not set an environment variable (described previously), you must authenticate in the command line. In the examples below, you include the storage password or secret key as part of the destination path. You are prompted for the transfer user's password upon running these commands unless you have set the `ASPERA_SCP_PASS` environment variable or are using an SSH key, as described above.

Storage Platform	ascp Syntax and Examples
Alibaba Cloud	Aspera recommends running <code>ascp</code> transfers with Alibaba Cloud with a docroot configured.
Amazon S3	<ul style="list-style-type: none"> <li>• If you are using IAM roles, you do not need to specify the access ID or secret key for your S3 storage.</li> </ul> <p>Upload syntax:</p> <pre>\$ ascp options --mode=send --user=username -- host=s3_server_addr source_files s3://access_id:secret_key@s3.amazonaws.com/destination</pre> <p>Upload example:</p> <pre>\$ ascp --mode=send --user=bear -- host=s3.asperasoft.com bigfile.txt s3://1K3C18FBWF9902:GEyU...AqXuxtTVHWtc@s3.amazonaws.com/ demos2014</pre>

Storage Platform	ascp Syntax and Examples
	<p>Download syntax:</p> <pre>\$ ascp options --mode=recv --user=username -- host=s3_server_addr s3://access_id:secret_key@s3.amazonaws.com/my_bucket/ my_source_path destination_path</pre> <p>Download example:</p> <pre>\$ ascp --mode=recv --user=bear --host=s3.asperasoft.com s3://1K3C18FBWF9902:GEyU...AqXuxtTVHWtc@s3.amazonaws.com/ demos2014/bigfile.txt /tmp/</pre>
Azure	<p>These examples are for Azure blob storage. For Azure Files, use the syntax: <code>azure-files://storage_account:storage_access_key@file.core.windows.net/share</code>. Aspera recommends running ascp transfers with Azure Data Lake Storage with a docroot configured.</p> <p>Upload syntax:</p> <pre>\$ ascp options --mode=send --user=username -- host=server_address source_files azu://storage_account:storage_access_k</pre> <p>Upload example:</p> <pre>\$ ascp --mode=send --user=AS037d8eda429737d6 -- host=dev920350144d2.azure.asperaondemand.com bigfile.txt azu://astransfer:zNfMtU...nBTkhB@blob.core.windows.net/abc</pre> <p>Download syntax:</p> <pre>\$ ascp options --mode=recv --user=username -- host=server azu://storage_account:storage_access_key@blob.core.windows.</pre> <p>Download example:</p> <pre>\$ ascp --mode=recv --user=AS037d8eda429737d6 -- host=dev920350144d2.azure.asperaondemand.com azu:// astransfer:zNfMtU...nBTkhB@blob.core.windows.net/abc / downloads</pre>
Google Cloud Storage	<p><b>Note:</b> The examples below require that the VMI running the Aspera server is a Google Compute instance.</p> <pre>\$ ascp options --mode=send --user=username -- host=server_address source_files gs:///my_bucket/my_path</pre> <p>Upload example:</p> <pre>\$ ascp --mode=send --user=bear --host=10.0.0.5 bigfile.txt gs:///2017_transfers/data</pre> <p>Download syntax:</p> <pre>\$ ascp options --mode=recv --user=username -- host=server gs:///my_bucket/my_path/source_file destination_path</pre>

Storage Platform	ascp Syntax and Examples
	Download example:  <pre>\$ ascp --mode=recv --user=bear --host=10.0.0.5 gs:///2017_transfers/data/bigfile.txt /data</pre>
HDFS	Aspera recommends running ascp transfers with HDFS with a docroot configured.
IBM COS - S3	Upload syntax:  <pre>\$ ascp options --mode=send --user=username -- host=server_address source_files s3://access_id:secret_key@accessor_end</pre> Upload example:  <pre>\$ ascp --mode=send --user=bear -- host=s3.asperasoft.com bigfile.txt s3://3ITI3OIUFEH233:KrcEW...AIuwQ@38.123.76.24/demo2017</pre> Download syntax:  <pre>\$ ascp options --mode=send --user=username -- host=server_address s3://access_id:secret_key@accessor_endpoint/vault_n source_files destination_path</pre> Download example:  <pre>\$ ascp --mode=send --user=bear --host=s3.asperasoft.com s3://3ITI3OIUFEH233:KrcEW...AIuwQ@38.123.76.24/demo2017 / tmp/</pre>
IBM Cloud Object Storage (COS) - Swift	Aspera recommends running ascp transfers with IBM Cloud Object Storage (COS) - Swift with a docroot configured.
OpenStack Swift	Upload syntax:  <pre>\$ ascp options --mode=send --user=username -- host=ip_addr source_files swift://account_id:api_key@auth_url/my_bucket</pre> Example Upload:  <pre>\$ ascp --mode=send --user=bear -- host=192.155.218.130 bigfile.txt swift:// XYZO...46-2:bob:437e...bc16@sjc01.objectstorage.service.networklayer.co test</pre> Download syntax:  <pre>\$ ascp options --mode=recv --user=username -- host=ip_addr swift://account_id:api_key@auth_url/my_bucket/ my_source_path destination_path</pre> Download example:  <pre>\$ ascp --mode=recv --user=bear --host=192.155.218.130 swift://</pre>

Storage Platform	ascp Syntax and Examples
	<pre>XYZO...46-2:bob:437e29...f616@sjc01.objectstorage.service.networklayer.com/test/bigfile.txt /tmp/</pre> <p><b>Note:</b> Swift requires additional Trapd configuration settings that can be included as queries attached to the docroot, with the format <i>docroot?setting</i>.</p> <p>For example, for an upload to IBM COS - Swift, the path is written as follows:</p> <pre>swift:// XYZO...46-2:bob:437e...bc16@sjc01.objectstorage.service.networklayer.com/test?aspera.swift.endpoint.auth-path=/auth/v1.0</pre>

## Writing Custom Metadata for Objects in Object Storage

Files uploaded to metadata-compatible storage (S3, Google Cloud, Azure, and Swift) can have custom metadata written with them by using the `--tags` or `--tags64` option. The argument is a JSON payload that specifies the metadata, and that is base64 encoded if it is used as an argument for `--tags64`.

### Metadata Behavior

- All objects that are uploaded in a session have the same metadata.
- If an upload resumes, the metadata of the original transfer is used.
- Multi-session transfers must specify the same metadata.
- Metadata are not retrieved when using `ascp` to download objects; use the REST API associated with the storage.
- Transfers to object storages that do not support metadata (such as HDFS and Azure Files) fail if metadata is specified.

### Specifying Metadata in JSON

The JSON payload has the general syntax of key-value pairs within a "cloud-metadata" section:

```
{
  "aspera": {
    "cloud-metadata": [
      {"key1": "value1"},
      {"key2": "value2"},
      ...
    ]
  }
}
```

Restrictions on key-value pairs:

- *key* cannot be `ctime`, `mtime`, or `atime`. These keys are reserved and the transfer fails if they are used.
- *key* might be case-sensitive, depending on the destination storage type.
- The key-value pair must be less than 1024 characters.

### Sample Ascp Session with Metadata

```
$ ascp --tags='{"aspera":{"cloud-metadata":[{"location":"skellig"}]}'
--mode=send --user=reynolds --host=s3.asperasoft.com sourcefile.mov s3://
s3.amazonaws.com/project
```

## Using Standard I/O as the Source or Destination

`ascp` can use standard input (stdin) as the source or standard output (stdout) as the destination for a transfer, usually managed by using the Aspera FASP Manager SDK. The syntax depends on the number of files in your transfer: for single files use `stdio://` and for multiple files use `stdio-tar://`. The transfer is authenticated using SSH or a transfer token.



## Named Pipes

A named pipe may be specified as a stdio destination, with the syntax `stdio:///path` for single files, or `stdio-tar:///path` for multiple files, where *path* is the path of the named pipe. If a `docroot` is configured on the destination, then the transfer goes to the named pipe `docroot/path`.

**Note:** Do not use `stdio:///path` to transfer multiple files. The file data is asynchronously concatenated in the output stream and might be unusable. Use `stdio-tar:///path` instead, which demarcates multiple files with headers.

## Single File Transfers

To upload data that is piped into `stdin`, set the source as `stdio:///?fsize`, where *fsize* is the number of bytes (as a decimal) that are received from `stdin`. The destination is set as the path and filename. The file modification time is set to the time at which the upload starts. Standard input must transfer the exact amount of data that is set by *fsize*. If more or less data is received by the server, an error is generated.

To download data and pipe it into `stdout`, set the destination as `stdio://`.

### Restrictions:

- `stdio://` cannot be used for persistent sessions. Use `stdio-tar://` instead.
- Only `--overwrite=always` or `--overwrite=never` are supported with `stdio://`. The behavior of `--overwrite=diff` and `--overwrite=diff+older` is undefined.

### Single-file Transfer Examples:

- Upload 1025 bytes of data from the client `stdin` to `/remote-dir` on the server at 10.0.0.2. Save the data as the file `newfile`. Transfer at 100 Mbps.

```
file_source | ascp -l 100m --mode=send --user=username --host=10.0.0.2
stdio:///?1025 /remote-dir/newfile
```

- Download the file `remote_file` from the server at 10.0.0.2 to `stdout` on the client. Transfer at 100 Mbps.

```
ascp -l 100m --mode=recv --user=username --host=10.0.0.2 remote_file
stdio://
```

- Upload the file `local_file` to the server at 10.0.0.2 to the named pipe `/tmp/outpipe`. Transfer at 100 Mbps.

```
ascp -l 100m --mode=send --user=username --host=10.0.0.2 local_file
stdio:///tmp/outpipe
```

## Multi-File Transfers

`ascp` can transfer one or more files in an encoded, streamed interface, similar to single file transfers. The primary difference is that the stream includes headers that demarcate data from individual files.

To upload files that are piped into `stdin`, set the source as `stdio-tar://`. The file modification time is set to the time at which the upload starts.

The file(s) in the input stream must be encoded in the following format. *File* can be the file name or file path, *Size* is the size of the file in bytes, and *Offset* is an optional parameter that sets where in the destination file to begin overwriting with the raw inline data:

```
[0 - n blank lines]
File: /path/to/file_1
Size: file_size
Offset: bytes

file_1 data
[0 - n blank lines]
```

```
File: /path/to/file_2
Size: file_size

file 2 data
...
```

To download one or more files to stdout, set the destination as `stdio-tar://`. Normal status output to stdout is suppressed during downloads because the transfer output is streamed to stdout. The data sent to stdout has the same encoding as described for uploads.

To download to a named pipe, set the destination to `stdio-tar:///path`, where *path* is the path of the named pipe.

When an offset is specified, the bytes that are sent replace the existing bytes in the destination file (if it exists). The bytes added to the destination file can extend beyond the current file size. If no offset is set, the bytes overwrite the file if overwrite conditions are met.

### Restrictions:

- When downloading to `stdio-tar://`, the source list must consist of individual files only. Directories are not allowed.
- Only `--overwrite=always` or `--overwrite=never` are supported with `stdio-tar://`. The behavior of `--overwrite=diff` and `--overwrite=diff+older` is undefined.
- Offsets are only supported if the destination files are located in the native file system. Offsets are not supported for cloud destinations.

### Multi-file Transfer Examples:

- Upload two files, `myfile1` (1025 bytes) and `myfile2` (20 bytes), to `/remote-dir` on the server at 10.0.0.2. Transfer at 100 Mbps.

```
cat sourcefile | ascp -l 100m --mode=send --user=username --host=10.0.0.2
stdio-tar:// /remote-dir
```

Where `sourcefile` contains the following:

```
File: myfile1
Size: 1025

<< 1025 bytes of data>>
File: myfile2
Size: 20

<<20 bytes of data>>
```

- Uploading multiple files from stdin by using a persistent session is the same as a non-persistent session.
- Update bytes 10-19 in file `/remote-dir/myfile1` on the server at 10.0.0.2 at 100 Mbps.

```
cat sourcefile | ascp -l 100m --mode=send --user=username --host=10.0.0.2
stdio-tar:// /remote-dir
```

Where `sourcefile` contains the following:

```
File: myfile1
Size: 10
Offset: 10

<< 10 bytes of data>>
```

- Upload two files, `myfile1` and `myfile2`, to the named pipe `/tmp/mypipe` (streaming output) on the server at 10.0.0.2. Transfer at 100 Mbps.

```
ascp -l 100m --mode=send --user=username --host=10.0.0.2 myfile1 myfile2
stdio-tar:///tmp/mypipe
```

This sends an encoded stream of `myfile1` and `myfile2` (with the format of `sourcefile` in the upload example) to the pipe `/tmp/mypipe`. If `/tmp/mypipe` does not exist, it is created.

- Download the files from the previous example from 10.0.0.2 to stdout. Transfer at 100 Mbps.

```
ascp -l 100m --mode=recv --user=username --host=10.0.0.2 myfile1 myfile2
stdio-tar://
```

Standard output receives data identical to `sourcefile` in the upload example.

- Download `/tmp/myfile1` and `/tmp/myfile2` to stdout by using a persistent session. Start the persistent session, which listens on management port 12345:

```
ascp -l 100m --mode=recv --keepalive -M 12345 --user=username --
host=10.0.0.2 stdio-tar://
```

Send the following in through management port 12345:

```
FASPMGR 2
Type: START
Source: /tmp/myfile1
Destination: mynewfile1

FASPMGR 2
Type: START
Source: /tmp/myfile2
Destination: mynewfile2

FASPMGR 2
Type: DONE
```

The destination must be a filename; file paths are not supported.

Standard out receives the transferred data with the following syntax:

```
File: mynewfile1
Size: file_size

mynewfile1_data
File: mynewfile2
Size: file_size

mynewfile2_data
```

- Upload two files, `myfile1` and `myfile2`, to named pipe `/tmp/mypipe` on the server at 10.0.0.2. Transfer at 100 Mbps.

```
ascp -l 100m --mode=send --user=username --host=10.0.0.2 myfile1 myfile2
stdio-tar:///tmp/mypipe
```

If `file/tmp/mypipe` does not exist, it is created.

- Upload two files, `myfile1` (1025 bytes) and `myfile2` (20 bytes) from `stdio` and regenerate the stream on the destination to send out through the named pipe `/tmp/mypipe` on the server at 10.0.0.2. Transfer at 100 Mbps.

```
cat sourcefile | ascp -l 100m --mode=send --user=username --host=10.0.0.2
stdio-tar:// stdio-tar:///tmp/pipe
```

Where sourcefile contains the following:

```
File: myfile1
Size: 1025

<< 1025 bytes of data>>
File: myfile2
Size: 20

<<20 bytes of data>>
```

## Applying Filters to Include and Exclude Files

Filters allow you to refine the list of files (or directories) designated for transfer. With filters, you indicate which files in the transfer list to skip or include. At runtime, `ascp` looks for filters in two locations: on the `ascp` command line, and in `aspera.conf`. Filters can be set in the `aspera.conf` file either from the GUI, or by modifying it directly with an editor or `asconfigurator`. When filtering rules are found in `aspera.conf`, they are applied *before* rules on the command line. If no filtering rules are specified, `ascp` transfers all source files in the transfer list. This topic describes filtering using option flags on the `ascp` command line.

**Note:** Filter settings apply only when the server is acting as a client. Servers cannot exclude files or directories uploaded or downloaded by remote clients.

### Specifying Rules on the Command Line

To specify filtering rules on the `ascp` command line, use the `-E` and `-N` options:

```
-E pattern   Exclude files or directories matching pattern.
-N pattern   Include files or directories matching pattern.
```

Each rule consists of a `-E` or `-N` option and its pattern. A pattern can be a file or directory name, or a set of names expressed with UNIX *glob* patterns.

To determine which files to transfer, each file in the set of source files to transfer (the transfer list) is evaluated by the filters as follows:

1. `ascp` compares the next file (or directory) in the transfer list to the first rule.
2. If the file matches the pattern, `ascp` includes it (`-N`) or excludes it (`-E`) and for this file, filtering stops.
3. If the file does not match, `ascp` compares it with the next rule and repeats the process for each rule until a match is found or until all rules have been tried.
4. If the file never matches any rules, it is included in the transfer.

Filtering operates only on the set of files and directories in the transfer list. That is, an include option (`-N`) cannot add files or directories that are not already part of the transfer list.

Filtering is a process of exclusion, and `-N` rules act as overrides to any `-E` rules that follow them. For example, consider the following example command:

```
$ ascp -N 'file2' -E 'file[0-9]' /tmp/L/file* user1@examplehost:/tmp
```

The transfer set is `file*` (all files that start with `file`). If `file1`, `file2`, and `fileA` are in `/tmp/L`, they are filtered as follows:

1. When `file1` is compared with the first rule (`-N`), no match is found, and filtering continues. When `file1` is compared with the second rule (`-E`), there is a match; `file1` is therefore excluded from transfer, and filtering stops for `file1`.
2. When `file2` is compared with the first rule, there is a match; `file2` is therefore included in the transfer, and filtering stops for `file2`.

3. When `fileA` is compared with the first rule, no match is found. When it is compared with the second rule, again no match is found. Because no further rules exclude it, `fileA` is therefore included in the transfer.

If directories or files reside in directories that have already been excluded, they will also be excluded and therefore not checked against any further rules. Thus, with the command-line options `-E '/above/' -N '/above/below'`, the file `/above/below` is never considered because its parent directory `/above/` has already been excluded.

### Creating Rule Patterns

In order to filter directories and files to be transferred, their names are matched against patterns (globs) that include wildcards and special characters. The patterns use the standard globbing syntax found in UNIX systems as well as several Aspera extensions to the standard.

Character case: Case always matters, even if the scanned file system does not enforce such a distinction. For example, "debug" does not match "Debug". To match both, the pattern should be "[Dd]debug".

Single quotes: Patterns must be interpreted only by `ascp`, not by the command shell. For this reason, patterns that contain wildcards should be surrounded by single quotes to protect them from expansion by the shell. (Even if patterns contain no wildcards, they can still be surrounded by single quotes.)

Partial matches: With globs, unlike standard regular expressions, the entire filename or directory name must match the pattern. That is, `abcdef` matches the pattern `abc*f` but `abcdefg` does not.

Pattern position: A pattern given with `-N` will match a path only if it falls directly under the transfer directory. However, a pattern given with `-E` will match a path regardless of where (which level) the path falls under the transfer directory. For example, given the pattern `'zzz*'` and a transfer directory `AAA`:

- The `-N` option matches only if the path to file (or directory) `zzz` falls *directly* under `AAA`. That is, `AAA/zzz`.
- The `-E` option matches regardless of where the path to file (or directory) `zzz` falls under `AAA`. For example, `AAA/abc/def/zzz`.

### Standard Globbing: Wildcards and Special Characters

/	The only recognized path separator.
\	Quotes any character literally, including itself. The <code>\</code> character is exclusively a quoting operator, not a path separator.
*	Matches zero or more characters, except a <code>/</code> , or the <code>.</code> when preceded immediately by a <code>/</code> character.
?	Matches any single character, except a <code>/</code> , or a <code>.</code> when preceded immediately by a <code>/</code> character.
[ ... ]	Matches exactly one of a set of characters, except a <code>/</code> or a <code>.</code> preceded immediately by a <code>/</code> character.
[ ^... ]	When <code>^</code> is the first character, matches exactly one character <i>not</i> in the set.
[ !... ]	When <code>!</code> is the first character, matches exactly one character <i>not</i> in the set.
[ x-x ]	Matches exactly one of a range of characters.
[ :xxxxx: ]	For details about this type of wildcard, see any POSIX-standard guide to globbing.

### Globbing Extensions: Wildcards and Special Characters

/**	Like <code>*</code> but also matches the <code>/</code> character, or a <code>.</code> preceded immediately by a <code>/</code> (that is, the <code>.</code> in <code>/. </code> ).
* or /** at end of pattern	Matches both directories and files.

/ at end of pattern	Matches directories only. With <code>-N</code> , no files under matched directories or their subdirectories are included in the transfer. All subdirectories are still included, although their files will not be included. However, with <code>-E</code> , excluding a directory also excludes all files and subdirectories under it.
no / or * at end of pattern	Matches files only.
/ at start of pattern	Must match the entire string from the root of the transfer set. (Note: The leading / does not refer to the system root or the docroot.)

### Standard Globbing Examples

Wildcard	Example	Matches	Does Not Match
/	abc/def/xyz	abc/def/xyz	abc/def
\	abc\?	abc?	abc\? abc/D abcD
*	abc*f	abcdef abc.f	abc/f abcefg
?	abc??	abcde abc.z	abcdef abc/d abc/.
[ ... ]	[abc]def	adef cdef	abcdef ade
[^... ]	[^abc]def	zdef .def 2def	bdef /def /.def
[!... ]	[!abc]def	zdef .def 2def	cdef /def /.def
[:xxxx:]	[[:lower:]]def	cdef ydef	Adef 2def .def

### Globbing Extension Examples

Wildcard	Example	Matches	Does Not Match
/**	a/**/f	a/f a./z/f a/d/e/f	a/d/f/ za/d/f
* at end of rule	abc*	abc/ abcfile	
** at end of rule	abc/**	abc/.file abc/d/e/	abc/
/ at end of rule	abc*/	abc/dir	abc/file
no / at end of rule	abc	abc (file)	abc/
/ at start of rule	/abc/def	/abc/def	xyz/abc/def

### Rule Composition

Example	Transfer Result
<code>-N rule</code>	Includes all files and directories whose names match <i>rule</i> . Because there is no <code>-E</code> , all the originally specified files and directories are included anyway; in other words, by itself, a <code>-N</code> rule does nothing.
<code>-N rule1 -E rule2</code>	Includes all files and directories whose names match <i>rule1</i> . Excludes all that match <i>rule2</i> , <i>except</i> those that also matched <i>rule1</i> .
<code>-E rule</code>	Excludes all files and directories whose names match <i>rule</i> .
<code>-E rule1 -N rule2</code>	Excludes all files and directories whose names match <i>rule1</i> . Because there is no <code>-E</code> following the <code>-N</code> , all files and directories not already excluded by the preceding <code>-E</code> are included anyway; in other words, a trailing <code>-N</code> rule does nothing to change the result.

## Testing Your Filter Rules

If you plan to use filtering rules, it's best to test them first. An easy way to test filtering rules, or to learn how they work, is to set up source and destination directories and use `demo.asperasoft.com` as the Aspera server:

1. On your computer, create a small set of directories and files that generally matches a file set you typically transfer. Since filenames are all that matter, the files can be small.
2. Place the file set in an accessible location, for example `/tmp/src`.
3. Upload the file set to the Aspera demo server as user "aspera". Specify the demo-server target directory `Upload`. You will be prompted for the password, which is "demoaspera":

```
$ ascp /tmp/src aspera@demo.asperasoft.com:Upload/
```

4. Create a destination directory on your computer, for example `/tmp/dest`.
5. You can now download your files from the demo server to `/tmp/dest`, running the `ascp` commands with `-N` and `-E` to test your filtering rules. For example:

```
$ ascp -N 'wxy/**' -E 'def' aspera@demo.asperasoft.com:Upload/src/abc/ /tmp/dest
```

6. Compare the destination directory with the source to determine whether files were filtered as expected.

```
$ diff -r dest/ src/
```

The `diff` output will show the missing (untransferred) files and directories.

## Example Filter Rules

The example rules below are based on running a command such as the following to download a directory `AAA` from `demo.asperasoft.com` to `/tmp/dest`:

```
$ ascp rules aspera@demo.asperasoft.com:Upload/AAA /tmp/dest
```

The examples below use the following file set:

```
AAA/abc/def
AAA/abc/.def
AAA/abc/.wxy/def
AAA/abc/wxy/def
AAA/abc/wxy/.def
AAA/abc/wxy/tuv/def
AAA/abc/xyz/def/wxy
AAA/wxyfile
AAA/wxy/xyx/
AAA/wxy/xyxfile
```

Key for interpreting example results below:

```
< xxx/yyy = Excluded
xxx/yyy = Included
zzz/ = directory name
zzz = filename
```

1. Transfer everything except files and directories starting with ".":

```
-N '*' -E 'AAA/**'
```

Results:

```
AAA/abc/def
AAA/abc/wxy/def
```

```

AAA/abc/wxy/tuv/def
AAA/abc/xyz/def/wxy
AAA/wxyfile
AAA/wxy/xyx/
AAA/wxy/xyxfile
< AAA/abc/.def
< AAA/abc/.wxy/def
< AAA/abc/wxy/.def

```

2. Exclude directories and files whose names start with `wxy`:

```
-E 'wxy*'
```

Results:

```

AAA/abc/def
AAA/abc/.def
AAA/abc/.wxy/def
AAA/abc/xyz/def/
< AAA/abc/wxy/def
< AAA/abc/wxy/.def
< AAA/abc/wxy/tuv/def
< AAA/abc/xyz/def/wxy
< AAA/wxyfile
< AAA/wxy/xyx/
< AAA/wxy/xyxfile

```

3. Include directories and files that start with "`wxy`" if they fall directly under `AAA`:

```
-N 'wxy*' -E 'AAA/**'
```

Results:

```

AAA/wxy/
AAA/wxyfile
< AAA/abc/def
< AAA/abc/.def
< AAA/abc/.wxy/def
< AAA/abc/wxy/def
< AAA/abc/wxy/.def
< AAA/abc/wxy/tuv/def
< AAA/abc/xyz/def/wxy
< AAA/wxy/xyx/
< AAA/wxy/xyxfile

```

4. Include directories and files at any level that start with `wxy`, but do not include dot-files, dot-directories, or any files under the `wxy` directories (unless they start with `wxy`). However, subdirectories under `wxy` will be included:

```
-N '*/wxy*' -E 'AAA/**'
```

Results:

```

AAA/abc/wxy/tuv/
AAA/abc/xyz/def/wxy
AAA/wxyfile
AAA/wxy/xyx/
< AAA/abc/def
< AAA/abc/.def
< AAA/abc/.wxy/def
< AAA/abc/wxy/def      *
< AAA/abc/wxy/.def
< AAA/abc/wxy/tuv/def

```



```
< AAA/wxy/xyxfile
```

\* Even though wxy is included, def is excluded because it's a file.

5. Include wxy directories and files at any level, even those starting with ".":

```
-N '*/wxy*' -N '*/wxy/**' -E 'AAA/**'
```

Results:

```
AAA/abc/wxy/def
AAA/abc/wxy/.def
AAA/abc/wxy/tuv/def
AAA/abc/xyz/def/wxy
AAA/wxyfile
AAA/wxy/xyx/
AAA/wxy/xyxfile
< AAA/abc/def
< AAA/abc/.def
< AAA/abc/.wxy/def
```

6. Exclude directories and files starting with wxy, but only those found at a specific location in the tree:

```
-E '/AAA/abc/wxy*'
```

Results:

```
AAA/abc/def
AAA/abc/.def
AAA/abc/.wxy/def
AAA/abc/xyz/def/wxy
AAA/wxyfile
AAA/wxy/xyx/
AAA/wxy/xyxfile
< AAA/abc/wxy/def
< AAA/abc/wxy/.def
< AAA/abc/wxy/tuv/def
```

7. Include the wxy directory at a specific location, and include all its subdirectories and files, including those starting with ".":

```
-N 'AAA/abc/wxy/**' -E 'AAA/**'
```

Results:

```
AAA/abc/wxy/def
AAA/abc/wxy/.def
AAA/abc/wxy/tuv/def
< AAA/abc/def
< AAA/abc/.def
< AAA/abc/.wxy/def
< AAA/abc/xyz/def/wxy
< AAA/wxyfile
< AAA/wxy/xyx/
< AAA/wxy/xyxfile
```

## Symbolic Link Handling

When transferring files using FASP (the Aspera GUI, ascp, ascp4, or async), you can configure how the server and client handle symbolic links.

**Note:** Symbolic links are not supported on Windows. Server settings are ignored on Windows servers. If the transfer destination is a Windows computer, the only supported option that the client can use is skip.

### Symbolic Link Handling Options and their Behavior

- **Follow:** Follow a symbolic link and transfer the contents of the linked file or directory as long as the link target is in the user's docroot.
- **Follow\_wide** (Server only): For downloads, follow a symbolic link and transfer the contents of the linked file or directory **even if the link target is outside of the user's docroot**. Use caution with this setting because it might allow transfer users to access sensitive files on the server.
- **Create** (Server only): If the client requests to copy symbolic links in an upload, create the symbolic links on the server.
- **None** (Server only): Prohibit clients from creating symbolic links on the server; with this setting clients can only request to follow or skip symbolic links.
- **Copy** (Client only): Copy only the symbolic link. If a file with the same name exists at the destination, **the symbolic link does not replace the file**.
- **Copy+force** (Client only): Copy only the symbolic link. If a file with the same name exists at the destination, **the symbolic link replaces the file**. If the file of the same name at the destination is a symbolic link to a directory, it is not replaced.

**Note:** A4 and Sync do not support the copy+force option.

- **Skip** (Client only): Skip symbolic links. Neither the link nor the file to which it points are transferred.

Symbolic link handling depends on the server configuration, the client handling request, and the direction of transfer, as described in the following tables. Multiple values can be set on the server as a comma-delimited list, such as the default "follow,create". In this case, the options are logically ORed based on the client's handling request.

#### Send from Client to Server (Upload)

	Server setting = create, follow (default)	Server setting = create	Server setting = follow	Server setting = follow_wide	Server setting = none
<b>Client setting = follow</b> (default for ascp and ascp4)	Follow	Follow	Follow	Follow	Follow
<b>Client setting = copy</b> (default for async)	Copy	Copy	Skip	Skip	Skip
<b>Client setting = copy+force</b>	Copy and replace any existing files.	Copy and replace any existing files.	Skip	Skip	Skip
<b>Client setting = skip</b>	Skip	Skip	Skip	Skip	Skip

#### Receive to Client from Server (Download)

	Server setting = create, follow (default)	Server setting = create	Server setting = follow	Server setting = follow_wide	Server setting = none
<b>Client setting = follow</b>	Follow	Skip	Follow	Follow even if the target is	Skip

	Server setting = create, follow (default)	Server setting = create	Server setting = follow	Server setting = follow_wide	Server setting = none
(default for ascp and ascp4)				outside the user's docroot.	
Client setting = copy (default for async)	Copy	Copy	Copy	Copy	Copy
Client setting = copy+force	Copy and replace any existing files.	Copy and replace any existing files.	Copy and replace any existing files.	Copy and replace any existing files.	Copy and replace any existing files.
Client setting = skip	Skip	Skip	Skip	Skip	Skip

## Server and Client Configuration

### Server Configuration

To set symbolic link handling globally or per user, run the appropriate command:

```
$ asconfigurator -x "set_node_data;symbolic_links,value"
$ asconfigurator -x "set_user_data;user_name,username;symbolic_links,value"
```

### Client Configuration

Transfers initiated in the GUI request that symbolic links be followed. This cannot be adjusted. To specify symbolic link handling on the command line (with `ascp`, `ascp4`, or `async`), use `--symbolic-links=option`.

## Creating SSH Keys (Command Line)

Public key authentication (SSH Key) is a more secure alternative to password authentication that allows users to avoid entering or storing a password, or sending it over the network. Public key authentication uses the client computer to generate the key-pair (a public key and a private key). The public key is then provided to the remote computer's administrator to be installed on that machine.

To log in into other Aspera servers with public key authentication, you can create key-pairs from the command line, as follows:

1. Create a `.ssh` directory in your home directory if it does not already exist:

```
$ mkdir /Users/username/.ssh
```

Go to the `.ssh` folder:

```
$ cd /Users/username/.ssh
```

2. Run `ssh-keygen` to generate an SSH key-pair.

Run the following command in the `.ssh` folder to create a key pair. For `key_type`, specify either RSA (`rsa`) or DSA (`dsa`). Aspera strongly recommends using the more secure RSA-type key. At the prompt for the key-pair's filename, press ENTER to use the default name `id_rsa` or `id_dsa`, or enter a different name, such as your username. For a passphrase, either enter a password, or press return twice to leave it blank:

```
$ ssh-keygen -t key_type
```

**Note:** When you run `ascp` in FIPS mode (`<fips_enabled>` is set to `true` in `aspera.conf`), and you use passphrase-protected SSH keys, you must either (1) use keys generated by running `ssh-keygen` in a FIPS-enabled system, or (2) convert existing keys to a FIPS-compatible format using a command such as the following:

```
$ openssl pkcs8 -topk8 -v2 aes128 -in id_rsa -out new-id_rsa
```

### 3. Retrieve the public key file.

The key-pair is generated to your home directory's `.ssh` folder. For example, assuming you generated the key with the default name `id_rsa`:

```
/Users/username/.ssh/id_rsa.pub
```

Provide the public key file (for example, `id_rsa.pub`) to your server administrator so that it can be set up for your server connection.

### 4. Start a transfer using public key authentication with the `ascp` command.

To transfer files using public key authentication on the command line, use the option `-i private_key_file`. For example:

```
$ ascp -T -l 10M -m 1M -i ~/.ssh/id_rsa myfile.txt jane@10.0.0.2:/space
```

In this example, you are connecting to the server (`10.0.0.2`, directory `/space`) with the user account `jane` and the private key `~/.ssh/id_rsa`.

## Client-Side Encryption at Rest (EAR)

---

Aspera clients can set their transfers to encrypt content that they upload to a server while it is in transit and stored on the server. The client specifies a password and the files are uploaded to the server with a `.aspera-env` extension. Anyone downloading these `.aspera-env` files must have the password to decrypt them, and decryption can occur during download or later.

You can combine client-side and server-side EAR, in which case files are doubly encrypted on the server.

Servers can require client-side encryption. In this case, transfer that do not use client-side EAR fail with the error message, "Error: Server aborted session: Server requires content protection."

**Note:** Client-side encryption-at-rest is supported only for `ascp` transfers, and is not supported for `ascp4` or `async` transfers.

### Using Client-Side EAR

Client-side EAR can be set in the GUI or on the `ascp` command line.

**GUI:** Go to **Connections > connection\_name > Security**. Select **Encrypt uploaded files with a password** and set the password. Select **Decrypt password-protected files downloaded** and enter the password.

**Ascp command line:** First, set the encryption and decryption password as the environment variable `ASPERA_SCP_FILEPASS`:

```
$ export ASPERA_SCP_FILEPASS=password
```

For uploads (`--mode=send`), use `--file-crypt=encrypt`. For downloads (`--mode=recv`), use `--file-crypt=decrypt`.

```
$ ascp --mode=send --file-crypt=encrypt source_file user@host:/remote_destination
$ ascp --mode=recv --file-crypt=decrypt user@host:/source_path/file.aspera-env local_destination
```

For more command line examples, see [Ascp General Examples](#) on page 64.

**Note:** When a transfer to Connect Server falls back to HTTP or HTTPS, client-side EAR is no longer supported. If HTTP fallback occurs while uploading, then the files are NOT encrypted. If HTTP fallback occurs while downloading, then the files remain encrypted.

### Encrypting and Decrypting Files Outside of a Transfer

For particularly sensitive content, do not store unencrypted content on any computer with network access. Use an external drive to physically move encrypted files between computers. Desktop Client include the `asprotect` and `asunprotect` command-line tools that can be used to encrypt and decrypt files.

- To encrypt a file before moving it to a computer with network access, run the following command:

```
$ export ASPERA_SCP_FILEPASS=password;/Library/Aspera/bin/asprotect -
o file1.aspera-env file1
```

- To download client-side-encrypted files without decrypting them immediately, run the transfer without decryption enabled (unselect **Decrypt password-protected files downloaded** in the GUI or do not specify `--file-encrypt=decrypt` on the `ascp` command line).
- To decrypt encrypted files once they are on a computer with no network access, run the following command:

```
$ export ASPERA_SCP_FILEPASS=password;/Library/Aspera/bin/asunprotect -
o file1 file1.aspera-env
```

## Comparison of Ascp and Ascp4 Options

Many command-line options are the same for `ascp` and `ascp4`; however, some options are available for only one or the behavior of an option is different. The following table lists the options that are available only for `ascp` or `ascp4`, and the options that are available with both. If the option behavior is different, the `ascp` option has **\*\*** added to the end and the difference is described following the table.

ascp	ascp4
-6	
-@ [range_low:range_high]	
-A, --version	-A, --version
--apply-local-docroot	
-C nodeid:nodecount	
-c cipher	-c cipher
--check-sshfp=fingerprint	
	--chunk-size=bytes
	--compare=method
	--compression=method
	--compression-hint=num
-D   -DD   -DDD	
-d	
	--delete-before
--delete-before-transfer**	--delete-before-transfer**

<b>ascp</b>	<b>ascp4</b>
--dest64	
-E <i>pattern</i>	-E <i>pattern</i>
-e <i>prepost_filepath</i>	
	--exclude-newer-than= <i>mtime</i>
	--exclude-older-than= <i>mtime</i>
-f <i>config_file</i>	
	--faspmgr-io
--file-checksum= <i>hash</i>	
--file-encrypt={encrypt decrypt}	
--file-list= <i>filepath**</i>	--file-list= <i>filepath**</i>
--file-manifest={none text}	
--file-manifest-path= <i>directory</i>	
--file-manifest-inprogress-suffix= <i>suffix</i>	
--file-pair-list= <i>filepath</i>	
-G <i>write_size</i>	
-g <i>read_size</i>	
-h, --help	-h, --help
-i <i>private_key_file_path**</i>	-i <i>private_key_file_path</i>
-K <i>probe_rate</i>	
-k {0 1 2 3}	-k {0 1 2 3}
--keepalive	--keepalive
-l <i>max_rate</i>	-l <i>max_rate</i>
-L <i>local_log_dir[:size]</i>	-L <i>local_log_dir[:size]</i>
-m <i>min_rate</i>	-m <i>min_rate</i>
	--memory= <i>bytes</i>
	--meta-threads= <i>num</i>
--mode={send recv}	--mode={send recv}
--move-after-transfer= <i>archivedir</i>	
--multi-session-threshold= <i>threshold</i>	
-N <i>pattern</i>	-N <i>pattern</i>
	--no-open
	--no-read
	--no-write
-O <i>fasp_port</i>	-O <i>fasp_port</i>

<b>ascp</b>	<b>ascp4</b>
--overwrite= <i>method</i> **	--overwrite= <i>method</i> **
-P <i>ssh-port</i>	-P <i>ssh-port</i>
-p	-p
--partial-file-suffix= <i>suffix</i>	
--policy={fixed high fair low}	--policy={fixed high fair low}
--precalculate-job-size	
--preserve-access-time	
--preserve-acls= <i>mode</i>	
--preserve-creation-time	
--preserve-file-owner-gid	--preserve-file-owner-gid
--preserve-file-owner-uid	--preserve-file-owner-uid
--preserve-modification-time	
--preserve-source-access-time	
--preserve-xattrs= <i>mode</i>	
--proxy= <i>proxy_url</i>	
-q	-q
-R <i>remote_log_dir</i>	-R <i>remote_log_dir</i>
	--read-threads= <i>num</i>
	--remote-memory= <i>bytes</i>
--remote-preserve-acls= <i>mode</i>	
--remote-preserve-xattrs= <i>mode</i>	
--remove-after-transfer	
--remove-empty-directories	
--remove-empty-source-directory	
	--resume (similar to -k)
--retry-timeout= <i>secs</i>	
-S <i>remote_ascp</i>	
--save-before-overwrite	
	--scan-threads= <i>num</i>
--source-prefix= <i>prefix</i>	
--source-prefix64= <i>prefix</i>	
	--sparse-file
--src-base= <i>prefix</i>	--src-base= <i>prefix</i>
--symbolic-links= <i>method</i> **	--symbolic-links= <i>method</i> **

ascp	ascp4
-T	-T
-u <i>user_string</i>	-u <i>user_string</i>
--user= <i>username</i>	--user= <i>username</i>
-v	
-W <i>token_string</i>   @ <i>token_filepath</i>	
-w{r f}	
-X <i>rexmsg_size</i>	-X <i>rexmsg_size</i>
-Z <i>dgram_size</i>	-Z <i>dgram_size</i>

### Differences in Option Behavior

#### --delete-before-transfer

With `ascp4`, `--delete-before-transfer` can be used with URI storage. URI storage is not supported for this option in `ascp`.

#### --file-list

`ascp` automatically applies `-d` if the destination folder does not exist. With `ascp4`, you must specify `-d`, otherwise all the files in the filelist are written to a single file.

#### -i (SSH key authentication)

With `ascp`, the argument for `-i` can be just the file name of the private key file and `ascp` automatically looks in the `.ssh` directory of the user's home directory. With `ascp4`, the full or relative path to the private key file must be specified.

#### --overwrite=*method*

The default overwrite method is "diff" for `ascp` and "always" for `ascp4`.

#### --symbolic-links

Both `ascp` and `ascp4` support follow, copy, and skip, but only `ascp` supports copy+force.

## Ascp FAQs

---

### 1. How do I control the transfer speed?

You can specify a transfer policy that determines how a FASP transfer utilizes the network resource, and you can specify target and minimum transfer rates where applicable. In an `ascp` command, use the following flags to specify transfer policies that are fixed, fair, high, or low:

Policy	Command template
Fixed	<code>--policy=fixed -l <i>target_rate</i></code>
Fair	<code>--policy=fair -l <i>target_rate</i> -m <i>min_rate</i></code>
High	<code>--policy=high -l <i>target_rate</i> -m <i>min_rate</i></code>
Low	<code>--policy=low -l <i>target_rate</i> -m <i>min_rate</i></code>



The policies have the following characteristics:

#### high

Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, the transfer rate is twice as fast as a fair-policy transfer. The `high` policy requires maximum (target) and minimum transfer rates.

#### fair

Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, bandwidth is shared fairly by transferring at an even rate. The `fair` policy requires maximum (target) and minimum transfer rates.

#### low

Adjust the transfer rate to use the available bandwidth up to the maximum rate. Similar to fair mode, but less aggressive when sharing bandwidth with other network traffic. When congestion occurs, the transfer rate is reduced to the minimum rate until other traffic decreases.

#### fixed

Attempt to transfer at the specified target rate, regardless of network or storage capacity. This can decrease transfer performance and cause problems on the target storage. Aspera discourages using the `fixed` policy except in specific contexts, such as bandwidth testing. The `fixed` policy requires a maximum (target) rate.

## 2. What transfer speed should I expect? How do I know if something is "wrong" with the speed?

Aspera's FASP transport has no theoretical throughput limit. Other than the network capacity, the transfer speed may be limited by rate settings and resources of the computers. To verify that your system's FASP transfer can fulfill the maximum bandwidth capacity, prepare a client machine to connect to this computer, and test the maximum bandwidth.

**Note:** This test typically occupies most of a network's bandwidth. Aspera recommends this test be performed on a dedicated file transfer line or during a time of low network activity.

On the client machine, start a transfer with fixed bandwidth policy. Start with a lower transfer rate and gradually increase the transfer rate toward the network bandwidth (for example, 1 MB, 5 MB, 10 MB, and so on). Monitor the transfer rate; at its maximum, it should be slightly below your available bandwidth:

```
$ ascp -l 1m source-file destination
```

To improve the transfer speed, also consider upgrading the following hardware components:

Component	Description
Hard disk	The I/O throughput, the disk bus architecture (such as RAID, IDE, SCSI, ATA, and Fiber Channel).
Network I/O	The interface card, the internal bus of the computer.
CPU	Overall CPU performance affects the transfer, especially when encryption is enabled.

## 3. How do I ensure that if the transfer is interrupted or fails to finish, it will resume without retransferring the files?

Use the `-k` flag to enable resume, and specify a resume rule:

- k 0 – Always retransfer the entire file.
- k 1 – Compare file attributes and resume if they match, and retransfer if they do not.
- k 2 – Compare file attributes and the sparse file checksums; resume if they match, and retransfer if they do not.
- k 3 – Compare file attributes and the full file checksums; resume if they match, and retransfer if they do not.

Corruption or deletion of the `.asp-meta` file associated with an incomplete transfer will often result in a permanently unusable destination file even if the file transfer resumed and successfully transferred.

#### 4. How does Aspera handle symbolic links?

The `ascp` command follows symbolic links by default. This can be changed using `--symbolic-links=method` with the following options:

##### **follow**

Follow symbolic links and transfer the linked files. (Default)

##### **copy**

Copy only the alias file. If a file with the same name is found at the destination, the symbolic link is not copied.

##### **copy+force**

Copy only the alias file. If a file (not a directory) with the same name is found at the destination, the alias replaces the file. If the destination is a symbolic link to a directory, it's not replaced.

##### **skip**

Skip symbolic links. Do not copy the link or the file it points to.

**Important:** On Windows, the only option is `skip`.

Symbolic link handling also depends on the server configuration and the transfer direction. For more information, see [Symbolic Link Handling](#) on page 81.

#### 5. What are my choices for overwriting files on the destination computer?

In `ascp`, you can specify the `--overwrite=method` rule with the following method options:

##### **never**

Never overwrite the file. However, if the parent folder is not empty, its access, modify, and change times may still be updated.

##### **always**

Always overwrite the file.

##### **diff**

Overwrite the file if different from the source. If a complete file at the destination is the same as a file on the source, it is not overwritten. Partial files are overwritten or resumed depending on the resume policy.

##### **diff+older**

Overwrite the file if older and also different than the source. For example, if the destination file is the same as the source, but with a different timestamp, it will not be overwritten. Plus, if the destination file is different than the source, but newer, it will not be overwritten.

##### **older**

Overwrite the file if its timestamp is older than the source timestamp.

**Interaction with resume policy (-k):** If the overwrite method is `diff` or `diff+older`, difference is determined by the resume policy (`-k {0|1|2|3}`). If `-k 0` or no `-k` is specified, the source and destination files are always considered different and the destination file is always overwritten. If `-k 1`, the source and destination files are compared based on file attributes (currently file size). If `-k 2`, the source and destination files are compared based on sparse checksums. If `-k 3`, the source and destination files are compared based on full checksums.

# ascp4: Transferring from the Command Line with Ascp4

---

## Introduction to Ascp4

---

Aspera Ascp4 is an optimized transfer engine based on FASP technology. Ascp4 is designed for sending extremely large sets of individual files efficiently. The executable, `ascp4`, is similar to `ascp` and shares many of the same options and capabilities, in addition to data streaming capabilities.

Both `ascp4` and `ascp` are automatically installed with IBM Aspera High-Speed Transfer Server, High-Speed Transfer Endpoint, and Desktop Client applications.

As installed, `ascp` is used for transfers initiated from the GUI and `ascp4` transfers can only be initiated from the command line. For information on how to make GUI-initiated transfers use `ascp4`, see [Using Ascp4 from the GUI](#) on page 99.

## Ascp4 Command Reference

---

Supported environment variables, the general syntax, and command options for `ascp4` are described in the following sections. `ascp4` exits with a 0 on success or a 1 on error. The error code is logged in the `ascp4` log file.

**Note:** Not all `ascp` options are available with `ascp4`. For more information, see [Comparison of Ascp and Ascp4 Options](#) on page 85. Additionally, `ascp4` transfers fail if the user's docroot is a symlink, whereas `ascp` supports symlink docroots.

### ascp4 Syntax

```
ascp4 options [[user@]srcHost:]source_file1[,source_file2,...]
           [[user@]destHost:]dest_path
```

#### User

The username of the Aspera transfer user can be specified as part of the as part of the source or destination, whichever is the remote server or with the `--user` option. If you do not specify a username for the transfer, the local username is authenticated by default.

**Note:** If you are authenticating on a Windows machine as a domain user, the transfer server strips the domain from the username. For example, `Administrator` is authenticated rather than `DOMAIN\Administrator`. Thus, you must specify the domain explicitly.

#### Source and destination paths

- If there are multiple source arguments, then the target path must be a directory.
- To describe filepaths, use single quotes (') and forward slashes (/) on all platforms.
- To transfer to the transfer user's docroot, specify "." as the destination.
- Avoid the following characters in filenames: / \ " : ' ? > < & \* |.
- If the destination is a symbolic link, then the file is written to the target of the symbolic link. However, if the symbolic link path is a relative path to a file (not a directory) and a partial file name suffix is configured on the receiver, then the destination path is relative to the user's home directory. Files within directories that are sent to symbolic links that use relative paths are not affected.

**URI paths:** URI paths are supported, but only with the following restrictions:

- If the source paths are URIs, they must all be in the same cloud storage account. No docroot (download), local docroot (upload), or source prefix can be specified.
- If a destination path is a URI, no docroot (upload) or local docroot (download) can be specified.

- The special schemes `stdio://` and `stdio-tar://` are supported only on the client side. They cannot be used as an upload destination or download source.
- If required, specify the URI passphrase as part of the URI or set it as an environment variable (`ASPERA_SRC_PASS` or `ASPERA_DST_PASS`, depending on the direction of transfer).

**UNC paths:** If the server is Windows and the path on the server is a UNC path (a path that points to a shared directory or file on Windows operating systems) then it can be specified in an `ascp4` command using one of the following conventions:

1. UNC path that uses backslashes (`\`)

If the client side is a Windows machine, the UNC path can be used with no alteration. For example, `\192.168.0.10\temp`. If the client is not a Windows machine, every backslash in the UNC path must be replaced with two backslashes. For example, `\\192.168.0.10\temp`.

2. UNC path that uses forward slashes (`/`)

Replace each backslash in the UNC path with a forward slash. For example, if the UNC path is `\192.168.0.10\temp`, change it to `//192.168.0.10/temp`. This format can be used with any client-side operating system.

## Environment Variables

If needed, you can set the following environment variables for use with an `ascp4` session.

**`ASPERA_SCP_PASS=password`**

The password that is used for SSH authentication of the transfer user.

**`ASPERA_SCP_TOKEN=token`**

Set the transfer user authorization token. `Ascp4` currently supports transfer tokens, which must be created by using `astokengen` with the `--full-paths` option. For more information, see "Transfer Token Generation (`astokengen`)" in the [IBM Aspera Enterprise Server Admin Guide](#).

**`ASPERA_SCP_COOKIE=cookie`**

A cookie string that is passed to monitoring services.

**`ASPERA_SRC_PASS=password`**

The password that is used to authenticate to a URI source.

**`ASPERA_DST_PASS=password`**

Set the password that is used to authenticate to a URI destination.

## Ascp4 Options

**`-A, --version`**

Display version and license information.

**`-c {aes128|aes192|aes256|none}`**

Encrypt in-transit file data using the specified cipher. This option overrides the `<encryption_cipher>` setting in `aspera.conf`.

**`--chunk-size=bytes`**

Perform storage read/write operations with the specified buffer size. Also use the buffer size as an internal transmission and compression block. Valid range: 4 Kb - 128 Mb. For transfers with object storage, use `--chunk-size=1048576` if chunk size is not configured on the server to ensure that the chunk size of `ascp4` and `Trapd` match.

**`--compare={size|size+mtime|md5|md5-sparse|sha1|sha1-sparse}method`**

When using `--overwrite` and `--resume`, compare files with the specified method. If the `--overwrite` method is `diff` or `diff+older`, the default `--compare` method is `size`.

**`--compression={none|zlib|lz4}`**

Compress file data inline. Default: lz4. If set to zlib, `--compression-hint` can be used to set the compression level.

**`--compression-hint=num`**

Compress file data to the specified level when `--compression` is set to an option that accepts compression level settings (currently only zlib). A lower value results in less, but faster, data compression (0 = no compression). A higher value results in greater, slower compression. Valid values are -1 to 9, where -1 is "balanced". Default: -1.

**`-D` | `-DD` | `-DDD`**

Log at the specified debug level. With each `D`, an additional level of debugging information is written to the log. This option is not supported if the transfer user is restricted to aspsell.

**`--delete-before`, `--delete-before-transfer`**

Before transfer, delete files that exist at the destination but not at the source. Requires write permissions on the destination. Objects on the destination that have the same name but different type or size as objects on the source are not deleted. Do not use with multiple sources, `--keepalive`, or HTTP fallback.

**`-E pattern`**

Exclude files or directories from the transfer based on the specified pattern. Use the `-N` option (include) to specify exceptions to `-E` rules. Rules are applied in the order in which they are encountered, from left to right. The following symbols can be used in the pattern:

- `*` (asterisk) represents zero or more characters in a string, for example `*.tmp` matches `.tmp` and `abcde.tmp`.
- `?` (question mark) represents a single character, for example `t?p` matches `tmp` but not `temp`.

For details and examples, see [Applying Filters to Include and Exclude Files](#) on page 76.

**Note:** When filtering rules are found in `aspera.conf`, they are applied *before* rules given on the command line (`-E` and `-N`).

**`--exclude-newer-than=mtime`**

**`--exclude-older-than=mtime`**

Exclude files (but not directories) from the transfer based on when the file was last changed. Positive `mtime` values are used to express time, in seconds, since the original system time (usually 1970-01-01 00:00:00). Negative `mtime` values (prefixed with "-") are used to express the number of seconds prior to the current time.

**`--faspmgr-io`**

Run `ascp4` in API mode using FASP manager I/O. `ascp4` reads FASPMGR4 commands from management and executes them. The FASPMGR4 commands are PUT/WRITE/STOP to open/write/close on a file on the server.

**`--file-list=filepath`**

Transfer the files and directories that are listed in `filepath`. Only the files and directories are transferred; path information is not preserved at the destination. Each source must be specified on a separate line, for example:

```
src
src2
...
srcN
```

To read a file list from standard input, use "-" in place of `filepath` (as `ascp4 --file-list=-`...). UTF-8 file format is supported. Use with `-d` if the destination folder does not exist.

**Restrictions:**

- Paths in file lists cannot use `user@host:filepath` syntax. You must use `--user` with `--file-list`.
- Only one `--file-list` option is allowed per `ascp4` session. If multiple file lists are specified, all but the last are ignored.
- Only files and directories from the file list are transferred, and any additional source files or directories specified on the command line are ignored.
- Because multiple sources are being transferred, the destination must be a directory.
- If the source paths are URIs, the size of the file list cannot exceed 24 KB.

For very large file lists (~100 MB+), use with `--memory` to increase available buffer space.

**-h, --help**

Display the usage summary.

**--host=host**

Transfer to the specified host name or address. Requires `--mode`. This option can be used instead of specifying the host as part of the filename (as `hostname:filepath`).

**-i private\_key\_file**

Authenticate the transfer using public key authentication with the specified SSH private key file (specified with a full or relative path). The private key file is typically in the directory `$HOME/.ssh/`. If multiple `-i` options are specified, only the last one is used.

**-k {0|1|2|3}**

Enable the resumption of partially transferred files at the specified resume level. Default: 0. This option must be specified for your first transfer or it does not work for subsequent transfers. Resume levels:

- `-k 0`: Always retransfer the entire file (same as `--overwrite=always`).
- `-k 1`: Compare file modification time and size and resume if they match (same as `--overwrite=diff --compare=size --resume`).
- `-k 2`: Compare sparse checksum and resume if they match (same as `--overwrite=diff --compare=md5-sparse --resume`).
- `-k 3`: Compare full checksum and resume if they match (same as `--overwrite=diff --compare=md5 --resume`).

**--keepalive**

Enable `ascp4` to run in persistent mode. This option enables a persistent session that does not require that source content and its destination are specified at execution. Instead, the persistent session reads source and destination paths through `mgmt` commands. Requires `--mode` and `--host`.

**-L local\_log\_dir[:size]**

Log to the specified directory on the client machine rather than the default directory. Optionally, set the size of the log file (default 10 MB).

**-l max\_rate**

Transfer at rates up to the specified target rate. Default: 10 Mbps. This option accepts suffixes "G/g" for Giga, "M/m" for Mega, "K/k" for Kilo, and "P/p/%" for percentage. Decimals are allowed. If this option is not set by the client, the server target rate is used. If a rate cap is set in the local or server `aspera.conf`, then the rate does not exceed the cap.

**-m min\_rate**

Attempt to transfer no slower than the specified minimum transfer rate. Default: 0. If this option is not set by the client, then the server's `aspera.conf` setting is used. If a rate cap is set in the local or server `aspera.conf`, then the rate does not exceed the cap.

**--memory=bytes**

Allow the local `ascp4` process to use no more than the specified memory. Default: 256 MB. See also `--remote-memory`.

**--meta-threads=*num***

Use the specified number of directory "creation" threads (receiver only). Default: 2.

**--mode={*send*|*recv*}**

Transfer in the specified direction: `send` or `recv` (receive). Requires `--host`.

**-N *pattern***

Protect ("include") files or directories from exclusion by any `-E` (exclude) options that follow it. Files and directories are specified using *pattern*. Each option-plus-pattern is a *rule*. Rules are applied in the order (left to right) in which they're encountered. Thus, `-N` rules protect files only from `-E` rules that follow them. Create patterns using standard globbing wildcards and special characters such as the following:

- `*` (asterisk) represents zero or more characters in a string, for example `*.tmp` matches `.tmp` and `abcde.tmp`.
- `?` (question mark) represents any single character, for example `t?p` matches `tmp` but not `temp`.

For details on specifying patterns and rules, including examples, see [Applying Filters to Include and Exclude Files](#) on page 76.

**Note:** Filtering rules can also be specified in `aspera.conf`. Rules found in `aspera.conf` are applied *before* any `-E` and `-N` rules specified on the command line.

**--no-open**

In test mode, do not actually open or write the contents of destination files.

**--no-read**

In test mode, do not read the contents of source files.

**--no-write**

In test mode, do not write the contents of destination files.

**-O *fasp\_port***

Use the specified UDP port for FASP transfers. Default: 33001.

**--overwrite={*always*|*never*|*diff*|*diff+older*|*older*}**

Overwrite files at the destination with source files of the same name based on the *method*. Default: `always`. Use with `--compare` and `--resume`. *method* can be the following:

- `always` – Always overwrite the file.
- `never` – Never overwrite the file. If the destination contains partial files that are older or the same as the source files and `--resume` is enabled, the partial files resume transfer. Partial files with checksums or sizes that differ from the source files are not overwritten.
- `diff` – Overwrite the file if it is different from the source, depending on the `compare` method (default is `size`). If the destination is object storage, `diff` has the same effect as `always`.

If `resume` is not enabled, partial files are overwritten if they are different from the source, otherwise they are skipped. If `resume` is enabled, only partial files with different sizes or checksums from the source are overwritten; otherwise, files resume.

- `diff+older` – Overwrite the file if it is older and different from the source, depending on the `compare` method (default is `size`). If `resume` is not enabled, partial files are overwritten if they are older and different from the source, otherwise they are skipped. If `resume` is enabled, only partial files that are different and older than the source are overwritten, otherwise they are resumed.
- `older` – Overwrite the file if its timestamp is older than the source timestamp.

**-P *ssh-port***

Use the specified TCP port to initiate the FASP session. (Default: 22)

**-p**

Preserve file timestamps for access and modification time. Equivalent to setting `--preserve-modification-time`, `--preserve-access-time`, and `--preserve-creation-time`. Timestamp support in object storage varies by provider; consult your object storage documentation to determine which settings are supported.

On Windows, modification time may be affected when the system automatically adjusts for Daylight Savings Time (DST). For details, see the Microsoft KB article, <http://support.microsoft.com/kb/129574>.

On Isilon IQ OneFS systems, access time (`atime`) is disabled by default. In this case, `atime` is the same as `mtime`. To enable the preservation of `atime`, run the following command:

```
# sysctl efs.bam.atime_enabled=1
```

**--policy={fixed|high|fair|low}**

Transfer according to the specified policy:

- `fixed` – Attempt to transfer at the specified target rate, regardless of network capacity. Content is transferred at a constant rate and the transfer finishes in a guaranteed time. The `fixed` policy can consume most of the network's bandwidth and is not recommended for most types of file transfers. This option requires a maximum (target) rate value (`-l`).
- `high` – Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, the transfer rate is twice as fast as transfer with a fair policy. This option requires maximum (target) and minimum transfer rates (`-l` and `-m`).
- `fair` – Adjust the transfer rate to fully utilize the available bandwidth up to the maximum rate. When congestion occurs, bandwidth is shared fairly by transferring at an even rate. This option requires maximum (target) and minimum transfer rates (`-l` and `-m`).
- `low` – Adjust the transfer rate to use the available bandwidth up to the maximum rate. Similar to fair mode, but less aggressive when sharing bandwidth with other network traffic. When congestion occurs, the transfer rate is reduced to the minimum rate until other traffic decreases.

If `--policy` is not set, `ascp4` uses the server-side policy setting (`fair` by default).

**--preserve-access-time**

Preserve the file timestamps (currently the same as `-p`).

**--preserve-creation-time**

Preserve the file timestamps (currently the same as `-p`).

**--preserve-file-owner-gid****--preserve-file-owner-uid**

(Linux, UNIX, and macOS only) Preserve the group information (`gid`) or owner information (`uid`) of the transferred files. These options require that the transfer user is authenticated as a superuser.

**--preserve-modification-time**

Preserve the file timestamps (currently the same as `-p`).

**--preserve-source-access-time**

Preserve the file timestamps (currently the same as `-p`).

**-q**

Run `ascp4` in quiet mode. This option disables the progress display.

**-R remote\_log\_dir**

Log to the specified directory on the remote host rather than the default directory. **Note:** Client users that are restricted to `aspsell` are not allowed to use this option.

**--read-threads=num**



Use the specified number of storage "read" threads (sender only). Default: 2. To set "write" threads on the receiver, use `--write-threads`.

**--remote-memory=bytes**

Allow the remote `ascp4` process to use no more than the specified memory. Default: 256 MB.

**--resume**

Resume a transfer rather than retransferring the content if partial files are present at the destination and they do not differ from the source file based on the `--compare` method. If the source and destination files do not match, then the source file is retransferred. See `-k` for another way to enable resume.

**--scan-threads=num**

Use the specified number of directory "scan" threads (sender only). Default: 2.

**--sparse-file**

Enable `ascp4` to write sparse files to disk. This option prevents `ascp4` from writing zero content to disk for sparse files; `ascp4` writes a block to disk if even one bit is set in that block. If no bits are set in the block, `ascp4` does not write the block (`ascp4` blocks are 64 KB by default).

**--src-base=prefix**

Strip the specified prefix from each source path. The remaining portion of the source path is kept intact at the destination. Available only in send mode. For usage examples, see [Ascp File Manipulation Examples](#) on page 66.

**Use with URIs:** The `--src-base` option performs a character-to-character match with the source path. For object storage source paths, the prefix must specify the URI in the same manner as the source paths. For example, if a source path includes an embedded passphrase, the prefix must also include the embedded passphrase otherwise it will not match.

**--symbolic-links={follow|copy|skip}**

Handle symbolic links using the specified method. For more information on symbolic link handling, see [Symbolic Link Handling](#) on page 81. On Windows, the only option is `skip`. On other operating systems, this option takes following values:

- `follow` – Follow symbolic links and transfer the linked files. (Default)
- `copy` – Copy only the alias file. If a file with the same name exists on the destination, the symbolic link is not copied.
- `skip` – Skip symbolic links. Do not copy the link or the file it points to.

**-T**

Disable in-transit encryption for maximum throughput.

**-u user\_string**

Define a user string for pre- and post-processing. This string is passed to the pre- and -post-processing scripts as the environment variable `$USERSTR`.

**--user=username**

Authenticate the transfer using the specified username. Use this option instead of specifying the username as part of the destination path (as `user@host:file`).

**Note:** If you are authenticating on a Windows machine as a domain user, the transfer server strips the domain from the username. For example, `Administrator` is authenticated rather than `DOMAIN\Administrator`. Thus, you must specify the domain explicitly.

**--worker-threads=num**

Use the specified number of worker threads for deleting files. On the receiver, each thread deletes one file or directory at a time. On the sender, each thread checks for the presences of one file or directory at a time. Default: 1.

**--write-threads=num**

Use the specified number of storage "write" threads (receiver only). Default: 2. To set "read" threads on the sender, use `--read-threads`.

For transfers to object or HDFS storage, write threads cannot exceed the maximum number of jobs that are configured for Trapd. Default: 15. To use more threads, open `/opt/aspera/etc/trapd/trapd.properties` on the server and set `aspera.session.upload.max-jobs` to a number larger than the number of write threads. For example,

```
# Number of jobs allowed to run in parallel for uploads.
# Default is 15
aspera.session.upload.max-jobs=50
```

### **-x** *rexmsg\_size*

Limit the size of retransmission requests to no larger than the specified size, in bytes. Max: 1440.

### **-z** *dgram\_size*

Use the specified datagram size (MTU) for FASP transfers. Range: 296-65535 bytes. Default: the detected path MTU.

As of v3.3, datagram size can be specified on the server by setting `<datagram_size>` in `aspera.conf`. The server setting overrides the client setting, unless the client is using a version of `ascp` that is older than 3.3, in which case the client setting is used. If the pre-3.3 client does not set `-z`, the datagram size is the discovered MTU and the server logs the message "LOG Peer client doesn't support alternative datagram size".

## Ascp4 Transfers with Object Storage

---

Files that are transferred with object storage are sent in chunks through Trapd. By default, `ascp4` uses 64 KB chunks and Trapd uses 1 MB chunks, but this mismatch in chunk size can cause `ascp4` transfers to fail.

To avoid this problem, take one of the following actions:

1. Set the chunk size (in bytes) in the server's `aspera.conf`. This value is used by both `ascp4` and Trapd, so the chunk sizes match.

To set a global chunk size, run the following command:

```
$ asconfigurator -x
"set_node_data;transfer_protocol_options_chunk_size,value"
```

Where *value* is between 256 KB (262144 bytes) and 1 MB (1048576 bytes).

To set a chunk size for the user, run the following command:

```
$ asconfigurator -x
"set_user_data;user_name, username;transfer_protocol_options_chunk_size,value"
```

2. Set the chunk size in the client's `aspera.conf` to the Trapd chunk size.

If Trapd is using the default chunk size, run the following command to set the chunk size to 1 MB:

```
$ asconfigurator -x
"set_node_data;transfer_protocol_options_chunk_size,1048576"
```

3. Set the chunk size in the client command line.

Run the `ascp4` session with the chunk size setting: `--chunk-size=1048576`.

## Ascp4 Examples

---

The commands for `ascp4` are generally similar to those for `ascp`, see [Ascp Command Reference](#) on page 50 and [Ascp Transfers with Object Storage and HDFS](#) on page 67 for examples, and [Comparison of Ascp and Ascp4 Options](#) on page 85 for option availability.

The following command examples demonstrate options that are unique to `ascp4`. These options enable reading management commands, enable read/write concurrency, and transfer TCP and UDP data streams.

- **Read FASP4 management commands**

Read management commands V4 from management port 5000 and execute the management commands. The management commands version 4 are PUT, WRITE and CLOSE.

```
$ ascp4 -L /tmp/client-logs -R /tmp/server-logs --faspmgr-io -M 5000
localhost:/tmp
```

- **Increase concurrency**

The following command runs `ascp4` with two scan threads and eight read threads on the client, and eight meta threads and 16 write threads on the server.

```
$ ascp4 -L /tmp/logs -R /tmp/logs -llg --scan-threads=2 --read-threads=8
--write-threads=16 --meta-threads=8 /data/100K aspera@10.0.113.53:/data
```

## Using Ascp4 from the GUI

---

Transfers initiated from the GUI use `ascp` and `ascp4` transfers can be run only from the command line. You can make transfers initiated from the GUI use `ascp4` by following these steps.

1. Back up the `ascp` executable.

Locate the `ascp` executable.

Rename the file `ascp-version.bak`.

2. In the same directory, make a copy of `ascp4` and rename it `ascp`.

The transfer server now uses `ascp4` for transfers initiated from the GUI.

**Important:** Not all standard `ascp` options are available with `ascp4`.

## Appendix

---

### Restarting Aspera Services

---

#### Aspera Central

If Aspera Central is stopped, or if you have modified the `<central_server>` or `<database>` sections in `aspera.conf`, then you need to restart the service.

Run the following command in a Terminal window to restart `asperacentral`:

```
$ sudo launchctl stop com.aspera.asperacentral
$ sudo launchctl start com.aspera.asperacentral
```

## Aspera NodeD

Restart Aspera NodeD if you have modified any setting in `aspera.conf`.

Run the following commands to restart `asperanoded`:

```
$ sudo launchctl stop com.aspera.asperanoded
$ sudo launchctl start com.aspera.asperanoded
```

## Testing and Optimizing Transfer Performance

To verify that your system's FASP transfer is reaching the target rate and can use the maximum bandwidth capacity, prepare a client machine to connect to this server. For these tests, you can transfer an existing file or file set, or you can transfer uninitialized data in place of a source file, which you can have destroyed at the destination, eliminating the need to read from or write to disk and saving disk space.

To send random data in place of a source file, run the following command:

```
$ ascp --mode=send --user=username --host=host_ip_address faux:///fname?fsize target_path
```

where *fname* is the name assigned to the file on the destination and *fsize* is the number of bytes to send. *fsize* can be set with modifiers (k/K, m/M, g/G, t/T, p/P, or e/E) up to 9 EB.

To send a file but not save the results to disk at the destination, run the following command:

```
$ ascp --mode=send --user=username --host=host_ip_address source_file1 faux://
```


To send random data and not save the results to disk, run the following command:

```
$ ascp --mode=send --user=username --host=host_ip_address faux:///fname?fsize faux://
```

For usage examples, see [Ascp General Examples](#) on page 64. Once you start a transfer from the command line, you can monitor it from the GUI.

1. Start a transfer with Fair transfer policy and compare the transfer rate to the target rate.

On the client machine, open the user interface and start a transfer (either from the GUI or command line). Click **Details** to open the Transfer Monitor.




To leave more network resources for other high-priority traffic, use the **Fair** policy and adjust the target rate and minimum rate by sliding the arrows or entering values.

## 2. Test the maximum bandwidth.

**Note:** This test will typically occupy a majority of the network's bandwidth. Aspera recommends performing it on a dedicated file transfer line or during a time of very low network activity.

Use **Fixed** policy for the maximum transfer speed. Start with a lower transfer rate and increase gradually toward the network bandwidth.



To improve the transfer speed, you may also upgrade the related hardware components:

Component	Description
Hard disk	The I/O throughput, the disk bus architecture (e.g. RAID, IDE, SCSI, ATA, and Fiber Channel).
Network I/O	The interface card, the internal bus of the computer.
CPU	Overall CPU performance affects the transfer, especially when encryption is enabled.

## aclean Reference

The Aspera `aclean` command-line tool is a fast method of deleting directories and files from local and object storage. Directories and files can be filtered based on their last modified times. For Windows operating systems, the created time (*CTIME*) and modified time (*MTIME*) are used as the matching criteria. You can do a dry run of an `aclean` command to test what content will be deleted. `aclean` can be run on any machine on which Aspera A4 is supported.

**Note:** The directory specified in an `aclean` command is not deleted. Only the content in the directory that matches the options is deleted.

### Syntax

```
aclean [options] directory
```

### Directory path format

- **Local paths:** Paths to local storage can be full or relative paths, and use "/" separators for all operating systems, including Windows. Full Windows paths must use the format `/c:/path/to/delete`.
- **Object storage:** Specify a path to object storage with its URI. For example, Azure storage has the syntax `azu://storage_account:storage_access_key@blob.core.windows.net/path_to_blob`

and a URL to AWS S3 has the syntax

`s3://access_id:secret_key@s3.amazonaws.com/my_bucket/path`. For more information on URL syntax for other object storage types, see [Ascp Transfers with Object Storage and HDFS](#) on page 67. The variable components of the URI must be URL encoded. For instructions on URL encoding, see [Aspera Enterprise Server Admin Guide \(Linux\): URL Encoding](#).

## Options

Option (short version, long version)	Description
<code>-h, --help</code>	Display help.
<code>-A, --version</code>	Display version.
<code>-L, --logdir</code>	Set the filepath for the log directory.
<code>-n, --dry-run</code>	Run the command as a trial to show what content would be deleted.
<code>-t, --threads</code>	Set the number of threads to use to scan the directory. (Default: 8)
<code>--remove-empty-dirs</code>	Delete empty subdirectories from the specified directory.
<code>--remove-newer-than=MTIME</code>	Delete files that are newer than <i>MTIME</i> . <i>MTIME</i> is a date and time string with the format YYYY-mm-dd HH:MM. The timestamp is based on the local time of the machine.
<code>--remove-older-than=MTIME</code>	Delete files that are older than <i>MTIME</i> . <i>MTIME</i> is a date and time string with the format YYYY-mm-dd HH:MM. The timestamp is based on the local time of the machine.

## Examples

Delete the contents of the local directory `/temp/logs-test/`:

```
$ aclean /temp/logs-test/
```

View what files would be deleted if `/temp/logs-test/` is deleted:

```
$ aclean --dry-run /temp/logs-test/
```

Delete subdirectories in `/temp/logs-test/` if they are empty:

```
$ aclean --remove-empty-dirs /temp/logs-test/
```


Delete files that have a last-modified time older than March 27, 2017 13:34 from Azure object storage:

```
$ aclean --remove-older-than=2017-03-27 13:34
azu://user:key@blob.microsoft.com
```

## Log Files

The log file includes detailed transfer information and can be useful for review and support requests.

To view the application log, go to **Tools > View Log**.




To review logs of other components, click **Open Logs Folder** to open the folder that contains transfer logs:

```
homedir/Library/Logs/Aspera/
```


The following files are available in the log folder. Older logs are stored with the same filename, appended with incremental numbers (e.g. ascmd.0.log).

File name	Contents
ascmd.log	File browsing and manipulation in the GUI
aspera-scp-transfer.log	FASP transfer events
async.log	Sync events

To set the logging level for transfers, open the **My Preferences** dialog by clicking **Tools > Preferences** or by clicking **Preferences** in the upper-right corner of the application window.



The five logging levels to select from are: **Off**, **Error**, **Warn**, **Info**, and **Debug**. The system default is **Info**.



## Accessing Shares from the GUI

As of Shares version 1.9.3, the client must have version 3.6.0 or later of Enterprise Server, Point-to-Point Client, or Desktop Client installed in order to access Shares on a server with version 3.6.0 or later of Enterprise Server, Point-to-Point Client, or Desktop Client installed.

**Note:** As of version 3.6.0, you can connect to Shares through the GUI, but command-line connection to Shares is not supported. To connect to Shares through the command line, you must download the Aspera CLI from the following location:

<http://downloads.asperasoft.com/en/downloads/62>

1. To access Shares from the GUI, go to **Connections** and click the **+** button.  
Enter the following information:

Field	Value	Example
Host	https:// <i>host_FQDN</i>	https://shares.asperasoft.com/
User	Shares username (of user with API Login enabled)	shares_user
Authentication	Shares user password	X45ape34_1

2. Click **Test Connection** to confirm your client application has successfully connected to Shares.
3. Click **Browse** to specify the target directory.
4. Click **OK** to save the connection.

## Product Limitations

Describes any limitations that currently exist for Aspera transfer server and client products.

- **Path Limit:** The maximum number of characters that can be included in *any* pathname is **4096 characters**.



- **Usernames with "@" symbol:** You cannot add a username with an "@" symbol through the Aspera GUI. You can, however, connect to and start a transfer with a Linux server through the Aspera GUI with user credentials containing the "@" symbol.

## Technical Support

---

### Support Websites

For an overview of IBM Aspera Support services, go to <https://asperasoft.com/company/support/>.

To view product announcements, webinars, and knowledgebase articles, as well as access the Aspera Support Community Forum, sign into the IBM Aspera Support site at <https://www.ibm.com/mysupport/> using your IBMid (not your company Aspera credentials), or set up a new account. Search for Aspera and select the product. Click **Follow** to receive notifications when new knowledgebase articles are available.

### Personalized Support

You may contact an Aspera support technician 24 hours a day, 7 days a week, through the following methods, with a guaranteed 4-hour response time.

Email	aspera-support@ibm.com
Phone (North America)	+1 (510) 849-2386, option 2
Phone (Europe)	+44 (0) 207-993-6653 option 2
Phone (Singapore)	+81 (0) 3-4578-9357 option 2

## Legal Notice

---

© 2005-2018 Aspera, Inc., an IBM Company. All rights reserved.

Licensed Materials - Property of IBM  
5725-S57

© Copyright IBM Corp., 2005, 2018. Used under license.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Aspera, the Aspera logo, and FASP transfer technology are trademarks of Aspera, Inc., registered in the United States. Aspera Connect Server, Aspera Drive, Aspera Enterprise Server, Aspera Point-to-Point, Aspera Client, Aspera Connect, Aspera Cargo, Aspera Console, Aspera Orchestrator, Aspera Crypt, Aspera Shares, the Aspera Add-in for Microsoft Outlook, Aspera FASPStream, and Aspera Faspex are trademarks of Aspera, Inc. All other trademarks mentioned in this document are the property of their respective owners. Mention of third-party products in this document is for informational purposes only. All understandings, agreements, or warranties, if any, take place directly between the vendors and the prospective users.